

Table of Contents

BV QSL Management and Label Printing - Version 7	4
Introduction	4
Foreword	4
About the author	4
Introduction	4
Copyright Information.....	6
Installation	6
Installation	6
Overview	7
Overview	7
BV Step by Step	8
BV Step-by-Step	8
Step 1 - Import the first log	8
Step 2 - Main Program Window.....	9
Step 3 - Log Window(s)	9
Step 4 - Log Search	10
Step 5 - Navigating through the Log	10
Step 6 - The Print Queue	11
BV Log Window	11
Command Overview	11
File	14
New log.....	14
Open log	15
Close log.....	15
Fill the Print Queue.....	16
Fill the Print Queue and Print	17
Label Print Options	17
Print Preview of Labels.....	18
Print Labels.....	18
Printer Setup.....	19
Options.....	19
Show Print Queue status.....	19
Empty Print Queue	20
Toggle Log Display Index.....	20
Set QSL sent flags	21
Set QSL received flags.....	22
Set QSL sent/rcvd date	22
Answering SWL Cards	23
Configuration	23
Configuration Overview	23
Configuration - General	24
Configuration - Combo Boxes.....	24
Configuration - Sorting.....	24
Configuration - Print Formats.....	26
Configuration - Slashed Zero.....	27
Configuration - Auto Open Logs	27
Configuration - BDE	27

Search.....	27
Search for Call, Band, Mode etc.	27
Filter for QSL sent and received flags.....	29
Filter marked QSO's.....	30
Wipe search fields.....	30
Log.....	30
Log Navigation.....	30
Selecting QSO records.....	31
Select row down.....	31
Select row up.....	32
Select all QSO's of this Call.....	32
Unselect.....	32
Fill Print Queue with selected QSO's.....	33
Fill QSO Record(s) with QSL Manager.....	33
Fill entire log with QSL Managers.....	33
Mark QSO.....	34
Remove all QSO Marks.....	34
Toggle QSL sent/received flags.....	34
Log Statistics.....	35
Footer Lines.....	35
Log Grid Setup.....	36
Windows.....	37
Label Designer.....	37
Tools (Import/Export).....	37
QSL Manager Database.....	37
QSO Edit Window.....	38
Print Queue Window.....	38
Jumping between Log Windows.....	38
Arranging the Log Windows.....	39
Reset all Dock Positions.....	39
Help.....	39
BV Label Designer	39
Label Designer Introduction.....	39
Basic Designer Window Options.....	40
Handling Elements.....	41
Layout Elements.....	43
Creating New Layouts.....	44
Modifying a Label Layout.....	44
Label Designer Command Overview.....	45
Label Frame Properties.....	46
Layout Elements.....	46
Data Fields.....	46
Text Elements.....	47
Expressions.....	48
Memo Fields.....	50
Shapes.....	51
Images.....	52
Layout Settings.....	52
Layout Settings.....	52
Label Type.....	53
Paper and Label Size.....	53
Number of QSO and Footer Lines.....	53
Design Tips.....	54
Add missing fields automatically.....	54
Adjust all QSO and footer lines.....	54
Analyze layout settings.....	55

Create layout template	55
BV Tools	56
BV Tools Overview	56
BV Tools Wizard	56
BV Tools Wizard.....	56
BV Tools Wizard - Choose Input Log(s).....	56
BV Tools Wizard - Choose Output Log	57
BV Tools Wizard - Specify fields to be exported	58
BV Tools Wizard - Write Mode	59
BV Tools Wizard - Converting.....	60
BV Tools Wizard - Log Macros.....	60
ASCII, CSV and dBase Import Specifications	60
ASCII and CSV File Import Specifications	60
ASCII and CSV File Import Specifications - Specifications.....	61
ASCII and CSV File Import Specifications - Text Type	61
ASCII and CSV File Import Specifications - Delimited File Type	61
ASCII and CSV File Import Specifications - Fixed File Type	62
ASCII and CSV File Import Specifications - Field Mapping	62
DBase Import Specifications	63
DBase Import Specifications - Specifications.....	63
DBase Import Specifications - Field Mapping	63
Date Format.....	64
Band/Freq Information.....	64
Log Types	64
Import Log Types	64
Export Log Types	67
ADIF - Amateur Data Interchange Format	67
ADIF Import into BV	68
Supported Bands.....	70
Supported Modes and Sub Modes.....	71
BV QSL Manager Database	74
QSL Manager Database	74
QSL Manager Window.....	75
QSL Manager Import	75
Printing the QSL Manager on Labels.....	77
Appendix	77
Glossary	77

BV QSL Management and Label Printing - Version 7

Welcome to BV Version 7 – the professional software for the QSL Management and Label/QSL Printing. This documentation explains all its features and includes a step-by-step introduction into BV.

Introduction

Foreword

Many of you know former versions of **BV**. The main reason to release Version 7 is a completely re-designed Visual QSL Label Designer. The BV Version 6 Label Designer was too complicated to use and did not offer the features and tools the user would expect from a professional design program.

The history of **BV** began as a DOS program in 1989 when the Bavarian Contest Club (BCC) had a major Contest DXpedition to Luxembourg as LX7A. As the QSL manager, I had to confirm some 30,000 QSO's then. The intension was to print as many different band QSO's as possible onto one single label - sorted by bands - and to ignore duplicate contacts.

Since then **BV** has gained many thousand users. The amount of labels printed with **BV** is not countable any more.

About the author

The author, Bernd Koch, DF3CB, is a radio amateur since 1976, very active as DXer and contester and working as a professional software developer.

<http://www.df3cb.com>

Introduction

BV is a professional software for the QSL Management and Label/QSL Printing under Windows® - developed and distributed by Bernd Koch, DF3CB, since 1989.

It is mainly designed for the contester and QSL manager with high QSL quantities but useful for all other QSL'ing purposes as well.

BV is freeware! **BV** is only available via the Internet. No mail delivery, no exceptions!

BV Website: <http://www.df3cb.com/bv>

Features

General

- Multiple log application - very useful for multi-call DXpeditions.
- Comfortable and fast log search capabilities.
- QSL manager database support plus manager import and export.
- Display logs sorted by call signs, chronologically (sorted by date and time) or by QSL managers, to find all stations that a particular manager handles.
- Answer SWL cards.

- Edit wrong log data.
- Footer Lines, Statistics etc.
- Start printing at label position # (label sheet saver).
- Includes all UHF/SHF and Microwave bands now, all new digital modes and sub modes.
- Reverse printing, print a range of pages.
- The QSL manager is now stored in the log to avoid confusion for stations with changing QSL managers.
- New log fields (columns) "Sub Mode" for all the new digital modes, "QSL Manager", "Date QSL sent" and "Date QSL received".
- Fully customizable log grid options.
- Unlike BV6, log sizes greater than app. 120,000 QSO's can be imported now into one log.
- The BDE (Borland Database Engine) does not need to be set anymore - BV7 sets all relevant parameters automatically.
- New improved setup program.

QSL Labels

- Print multiple QSO's (up to 18) for the same call sign on one common label.
- Label printing on any sizes and formats or direct printing on QSL's without labels.
- Many, many sort and select criteria for printing QSO's, e.g. ignore duplicate contacts.
- Sorted printout of QSL labels in accordance with the QSL bureau rules.
- Sorted printout of US call signs by call districts.
- Print particular selected or marked QSO's.
- Supports reports with 6 digits (like 599+20).

Visual QSL Label Designer

- Very flexible Visual Label Designer. Completely re-designed. No more try and error.
- 1490 predefined label formats from 31 manufacturers.
- Layout can completely be customized incl. colored printing, graphics etc.
- New layout wizard.
- Maximum of 18 QSO lines.
- Move and position layout elements precisely via the keyboard.
- Rotate text and data fields.
- Expressions (data fields plus text).

- Memo fields for large text.
- Support for JPEG image files.
- Cut, copy and paste of elements, undo function, send to back, bring to front.
- Grouping of elements.
- X-Y-position indicator for all elements.
- Add missing fields and QSO lines automatically.
- Analyze wrong layout settings.
- Create layout templates automatically.
- Double-click to change element attributes.
- Printer setup.
- File history.
- Prompt before closing a changed label layout (works now).
- Prints on any Windows®-supported printer.

Log Conversion Utility

- Great and flexible log import, export, log merge and maintenance capabilities. Completely redesigned.
- Imports 36 different logbook formats like ADIF (Amateur Data Interchange Format), any dBase, ASCII and CSV ("comma separated value" files), CT, NA, TRLog, WF1B and many others.
- Update mode when importing into existing logs.

Copyright Information

BV is copyright by Bernd Koch, DF3CB.

BV Website: <http://www.df3cb.com/bv>

Installation

Installation

BV Version 7 is designed for Windows 95, 98, NT, ME and 2000. It is important to read and follow these instructions before you download.

BDE (Borland Database Engine)

- BV requires a BDE (Borland Database Engine) installation on your computer. BV will not run without the BDE! The BDE is a set of database drivers and includes an administration program.
- The BDE installation is necessary only once.
- The BDE version needs to be at least 5.0!

- Users of BV Version 6 have usually BDE version 3.5 installed. If you want to upgrade to BV Version 7, you must upgrade your BDE installation to 5.0 - otherwise BV7 will not work! The upgrade will not overwrite your existing configuration and is compatible with BV6.
- Download the installation software **bde_setup.exe** for free at: <http://www.df3cb.com/bv/bvdl.html>. The file size is 3.9 MB.
- Save the file in a temporary folder on your hard disk (for example in C:\temp).
- When the download is finished, double-click on the file **bde_setup** in your temporary folder to start the installation of the BDE. Follow the instructions in the setup program. It is recommended to install it in the program folder C:\Program Files\BDE.
- With BV Version 7, the BDE does not have to be set up any more.

BV Version 7

- Download the installation software **bv7_setup.exe** for free at: <http://www.df3cb.com/bv/bvdl.html>. The file size is 1.5 MB.
- Save the file in a temporary folder on your hard disk (for example in C:\temp).
- When the download is finished, double-click on the file **bv7_setup** in your temporary folder to start the installation of BV7. Follow the instructions in the setup program. It is recommended to install it in the program folder C:\Program Files\BV7. **Do not install it in your BV6 program folder!**

BV Version 6 to 7 Upgrade

- Since the formats of the logs and layout files have changed, I have provided the upgrade program BV6to7. It is available at: <http://www.df3cb.com/bv/bvdl.html>. The program is packed in a ZIP file. The file size is 590 kB.
- When the download is finished, double-click on the file **bv6to7.zip**, unzip the file anywhere using an unzip program, for example WinZip. Run the extracted program BV6to7, after you have installed BV Version 7. It is self-explaining. You can convert all your label layouts, program settings and all or only particular log files.

Overview

Overview

BV consists of three major parts (windows):

- The main **Log Search Window**. See chapter **BV Step by Step Introduction** and **Command Overview**.
- The **Label Designer Window**. See chapter **Designer Introduction**.
- The **Tools Window**, a log import/export utility. See chapter **BV Tools**.

There are more sub windows and features like

- The **Configuration** dialog,
- The **SWL Mode** and
- The **QSL Manager** window.

BV Step by Step

BV Step-by-Step

There are always three ways to open sub windows or to perform program actions:

- Via the main **program menu**. Main Menu commands are highlighted in **red** in this documentation.
- By clicking on **buttons**. Buttons are highlighted in blue-green and are underlined in this documentation.
- By using special **shortcut keys**, e.g. **Ctrl**+**O**.

It is recommended to learn and use the shortcut keys.

The follow chapters give you a quick tour through BV:

[Step 1 - Import the first log](#)

[Step 2 - Main Program Window](#)

[Step 3 - Log Window\(s\)](#)

[Step 4 - Log Search](#)

[Step 5 - Navigating through the Log](#)

[Step 6 - The Print Queue](#)

Step 1 - Import the first log

Start **BV7**. The program starts with a splash (information) screen, which disappears as soon as the program and its configuration are initialized. The main (and still empty) **Log Window** opens first.

The first step is to create a BV log file by importing another log file. If you start BV for the first time, it notices that there no logs yet:

'There are no logs yet. Do you want to let BV create a sample log file?'

- Confirm with **Yes**.
- Click on the **Browse** button and select the file *sample.adi*.
- Enter your call sign and click on **Start Conversion**.
- Click on the **Finish** button after the quick import.
- The new created BV log will then automatically be opened.

Next step:

[Step 2 - Log Window Overview](#)

Step 2 - Main Program Window

Click on the [Maximize](#) system icon in the log window or press `Shift+Ctrl+M` to adjust the log window to the maximum size. Resize the entire program window by dragging the handle in the lower right corner to a convenient size

The **Main Program Window** consists of

- a [main menu](#),
- a [command toolbar](#),
- a [log search toolbar](#),
- the [print queue window](#),
- one or more [log windows](#) and
- a [status bar](#) at the bottom.

Some of these elements are not always visible or can be made invisible. The log search toolbar for example is only then visible when at least one log is open. The toolbars and the print queue window can be dragged and docked to other positions or "dock bars" by moving the left drag handle while you keep the left mouse button pressed. They can also be moved out of the main program window. The positions are saved and restored at next BV program start.

There are always three ways to perform commands and program actions:

- via the **main program menu**,
- by clicking on [buttons](#) *or*
- by using special [shortcut keys](#), e.g. `Ctrl+Q`.

It is recommended to learn and use the shortcut keys.

Next step:

[Step 3 - Log Window\(s\)](#)

Step 3 - Log Window(s)

The log window displays the entire log in a grid which has columns for information like call sign, date, time, band, mode and so on. Every QSO record is displayed (sorted) in rows. The log window contains additional information like the log's call sign or the number of selected records.

The appearance of the log grid can be customized in the [Log Grid Setup](#).


Next step:

[Step 4 - Log Search](#)

Step 4 - Log Search

BV uses an incremental log search method. This means that the log search will be performed after every keystroke or change of the combo box values in all open logs. Therefore you see your search results immediately.

Begin to enter a call sign you can see in the log, e.g. DL1IAO, into the left search field of the search toolbar:



While you enter the call sign, the incremental search mechanism tries to find the first QSO record that matches with the entered search values and displays a range of the log. As soon as there is an **exact (call sign) match**, only the QSO's for the particular match are displayed.

There are many more search fields in the search toolbar. They are used to apply further search and filter functions to the log. Use the **Tab** key or **Enter** key to jump to the next input field or use the shortcut keys:

Alt-C

Enter a particular **call sign** you want to lookup in the first field.

Alt-L

Optionally, a second call sign or prefix can be entered in the second call search field for **call sign range searches**. This is useful to limit the search results or the search range. Note that, due to the alphabetical character order, the prefix in this field has to be "greater" than in the first call search field. Otherwise there will be no results.

Alt-B

Band combo box. Choose a specific band by clicking on this combo box. The values of this combo box can be defined in the [Configuration - Combo Boxes](#)

Alt-M

Mode combo box. Choose a specific mode by clicking on this combo box. The values of this combo box can be defined in the [Configuration - Combo Boxes](#)

Pressing the function key **F11** clears all search fields.

Next step:

[Step 5 - Navigating through the Log](#)

Step 5 - Navigating through the Log

You can easily navigate through the log by using the cursor keys:

↓

Move to next QSO record

↑


Move to prior QSO record

Pg Dn

Move 10 QSO's forward

Pg Up

Move 10 QSO's backward

-  Move to last QSO record
-  Move to first QSO record

Next step:

[Step 6 - The Print Queue](#)

Step 6 - The Print Queue

One of the basic concepts of BV is the **Print Queue**. The print queue is a temporary container holding the data of the QSO's to be printed on QSL labels or QSL cards.

The QSO data is not immediately printed. Instead, it is first sent into the print queue. The purpose behind this idea is that the program has to wait at least so long until a full label sheet can be filled without losing expensive labels. The other, sometimes more practical reason is that you first can do your "paper work" and when having done that – print the labels. Another advantage is that you can exit the program and continue later – the print queue is still there.

There are several ways to put QSO's of the logs into the **print queue**, as this is the most frequently used BV function.

Press the  key now or click on the  button. The warning '*Do you want to print all calls?*' is issued but say **Yes** (Confirm simply with ). Watch the log window processing QSO's now and how the print queue window on the left fills. Watch also the number of created labels increasing in the status bar.

How and under which conditions the print queue is filled, can be defined in the [Configuration - Sorting](#).







More on filling the print queue is explained in the chapter [Fill the Print Queue](#).

The next steps are not yet available but will follow soon.

BV Log Window

Command Overview

File and Print Commands

		New log (only ADIF import)
		Open log
		Close log
		Fill Print Queue with QSOs of active log
		
		Fill Print Queue with QSOs of all open logs
		
		Label Print Options

	Ctrl + R	Print Preview of Labels
	Ctrl + P	Print Labels
		Printer Setup
	Ctrl + L	Load label design
	Alt + X	Exit BV

Options

	Ctrl + G	Configuration
	Ctrl + Q	Show Print Queue status
	Ctrl + E	Empty Print Queue
	F5	Toggle Log Display Index
	Shift + F5	Toggle Back Log Display Index
	Qs	Set QSL sent flags
	Qr	Set QSL received flags
	Shift + Ctrl + D	Set QSL sent/rcvd date
	Shift + Ctrl + A	Answer SWL Cards

Search Commands

	Alt + C	Jump to call search field. See: Search for Call, Band, Mode etc.
	Alt + R	Jump to second call search field (range search). See: Search for Call, Band, Mode etc.
	Alt + B	Jump to band search combo box. See: Search for Call, Band, Mode etc.
	Alt + M	Jump to mode search combo box. See: Search for Call, Band, Mode etc.
	Alt + D	Jump to date search field. See: Search for Call, Band, Mode etc.
	Alt + T	Jump to time search field. See: Search for Call, Band, Mode etc.
	Alt + E	Jump to second date search field (range search). See: Search for Call, Band, Mode etc.
	Alt + L	Jump to second time search field (range search). See: Search for Call, Band, Mode etc.

	<code>[Alt] + [G]</code>	Jump to manager search field. See: Search for Call, Band, Mode etc.
		Filter for QSL sent flags
		Filter for QSL received flags
	<code>[F7]</code>	Filter marked QSO's
	<code>[F11]</code>	Wipe search fields

Log Commands

	<code>[↓]</code>	Move to next QSO record. See: Log Navigation
	<code>[↑]</code>	Move to prior QSO record. See: Log Navigation
	<code>[Pg Dn]</code>	Move 10 QSO's forward. See: Log Navigation
	<code>[Pg Up]</code>	Move 10 QSO's backward. See: Log Navigation
	<code>[Ctrl] + [End]</code>	Move to the last QSO record. See: Log Navigation
	<code>[Ctrl] + [Home]</code>	Move to the first QSO record. See: Log Navigation
	<code>[Ctrl] + [A]</code>	Select all QSO's of this Call
	<code>[Shift] + [↓]</code>	Select row down
	<code>[Shift] + [↑]</code>	Select row up
	<code>[Esc]</code>	Unselect
	<code>[Ctrl] + [↔]</code>	Fill Print Queue with selected QSO's
	<code>[Alt] + [F7]</code>	Mark QSO
	<code>[Ctrl] + [F7]</code>	Remove all QSO Marks
	<code>[Ctrl] + [F]</code>	Fill QSO Record(s) with QSL Manager
	<code>[F8]</code>	Toggle QSL sent flags (N=no > Y=yes > B=bureau > D=direct > !=never)
	<code>[F9]</code>	Toggle QSL received flags (N > Y > B > D > !)
	<code>[Shift] + [Ctrl] + [S]</code>	Log Statistics
	<code>[Shift] + [Ctrl] + [F]</code>	Footer Lines
	<code>[Shift] + [Ctrl] + [G]</code>	Log Grid Setup

Windows Commands

	Ctrl · D	Show Label Designer Window
	Ctrl · T	Open the Tools Window (import/export)
	Ctrl · M	Open the QSL Manager Window
	F4	Show QSO Edit Window
	F10	Show Print Queue Window
	F6	Jump to next open log
	Shift · F6	Jump to previous open log
	Shift · Ctrl · C	Cascade log windows. See: Arranging the Log Windows
	Shift · Ctrl · H	Tile log windows horizontally. See: Arranging the Log Windows
	Shift · Ctrl · V	Tile log windows vertically. See: Arranging the Log Windows
	Shift · Ctrl · M	Maximize all log windows. See: Arranging the Log Windows

Help Commands

	F1	Show this help file
	Ctrl · F1	Search help file

File

New log

Create **new BV log files** via

- the main menu **File | New Log...** *or*
- by clicking on the  button in the main toolbar *or*
- by using the shortcut key **Shift**·**Ctrl**·**N**.

Note: Only ADIF (Amateur Data Interchange Format) files can be imported here! Most logbook types offer ADIF export. If you want to import other log types, choose the [Tools Window](#).

- Click on the [Browse](#) button to select an ADIF log to be imported.

- Specify a BV log file name. Just type the filename – log path and file extension are added automatically.
- Enter your call sign and finally
- Click on the [Start Conversion](#) button, as soon as it is enabled.
- Click on [Finish](#) to close the dialog as soon as the conversion (import) is finished

The just generated BV log can then be [opened](#).

See also:

[Open log](#)

[Close log](#)

Open log

Open BV log files via

- the main menu **File | Open Log** *or*
- by clicking on the  button in the main toolbar *or*
- by using the shortcut key **Ctrl+O**.

Press the **↓** key once – the first entry will be highlighted. Press a character for fast navigation if you have a long log file list. Press **Enter** to open one selected log file or click on the **Open** button.

Note: You can choose several logs to open at one time by keeping the **Ctrl** key pressed and selecting the files with mouse clicks or a range of log files by keeping the **Shift** key pressed. The bottom status bar displays how many files are selected and displays the call of the selected log.

Note: Close the window by pressing the **Esc** key if you want *no* action or click on the **Cancel** button.

Note: The logs are located in the sub folder logs of the BV7 program folder. Each log consists of three files: *logname.bv7*, *logname.dbf* and *logname.mdx*.

Note: Logs can automatically be opened at each BV program start if you specify the logs to be opened in the [Configuration - Auto Open Logs](#).

See also:

[Close log](#)

Close log

Close BV log files via

- the main menu **File | Close Log** *or*
- by clicking on the  button in the main toolbar *or*
- by clicking on the log window's close button in the upper right corner *or*
- by using the shortcut key **Ctrl+F4**.

Note: The open logs *do not need to be closed* explicitly *before* you exit BV.

See also:

Close log

Fill the Print Queue

Print Queue

There are several ways to put QSO's of the logs into the **print queue** as this is the most frequently used BV function. As explained above, the print queue is a temporary container holding the data of the QSO's to be printed on QSL labels or QSL cards. It collects data until a label sheet is full which then can be printed and it can also collect data from different, open logs.

F2

Usually one can say: "what you see is what you print". That's (almost) true, depending on the switches in the [Configuration - Sorting](#). If you see the entire log and press **F2** to fill the print queue, the entire log will be put in there indeed. If you have typed a particular call sign in the log search field for call signs, you will see only one or several QSO's in the log with this station. When you press **F2** now, only the QSO's for this particular call sign will be put into the print queue.

It is mentioned already – the shortcut key for this action is **F2**. Alternatively you can use

- the main menu item **File | Put QSO's of active Log in Print Queue** or
- by clicking on the  button in the main toolbar.

F3

If you have several logs open and want to let BV collect and print QSO data from all open logs for a particular call sign, press **F3** instead or click on the  button. QSL managers who get requests for several DXpedition calls in one envelope use this feature.

Because this function is used so frequently, there are other ways to fill the print queue.

Drag and Drop

You can drag QSO's from the open, active log into the **Print Queue Window** (the print queue window can be opened with the function key **F10**). Click the left mouse button. Hold down the button, drag the element to the print queue window on the left and release the mouse button. Only one QSO is transferred into the print queue, the one that is highlighted in the log.

Selecting QSO's

To put or drag and drop more than one QSO record into the print queue, you have to *select* particular QSO records.

- You can select multiple, non-contiguous rows by keeping the **Ctrl** key pressed and clicking on particular QSO rows.
- To select contiguous rows, keep the **Shift** key pressed and use the **↑** or **↓** keys.
- To select all QSO's for one particular station, press the shortcut key **Ctrl+A**.

All selected QSO records are highlighted and the number of selected records appears in the top panel of the active log window. A selection of QSO records can be put into the print queue with

- **F2** or
- Drag and drop or
- With the function key **Ctrl+⇐**

Cancel a selection

A selection can be cancelled by pressing the **Esc** key or by clicking on the select counter in the top panel of the active log.

Note: **F2** / **F3** fills the print queue according to the rules as set in the **Configuration - Sorting**, for example sorted printout chronologically or by bands or modes. If there is a QSO for a particular call already in the print queue and you perform another **F2** / **F3**, the program discovers this and *appends* the new data to the old one! The new QSO's are not merged but appended. This will break the rules as defined in the **Configuration - Sorting** but this can be useful at times.

Note: If some or all of your QSO's do *not* appear in the print queue, then your QSO's have apparently a "QSL sent flag" "Y = QSL sent" which means that the QSO was already printed in the past. If you want to print it nevertheless, change the settings in the **Configuration - Sorting**.

See also:

[Fill the Print Queue and Print](#)

[Show Print Queue status](#)

[Empty Print Queue](#)

Fill the Print Queue and Print

Shift + **F2** is used to fill the print queue *and* to print the label or QSL card directly after this action. This should only be used if you handle card by card and if you print directly on QSL cards. It shall not be used if you use label sheets with more than one label per page!

See also:

[Fill the Print Queue](#)

[Show Print Queue status](#)

[Empty Print Queue](#)

Label Print Options

 The **Label Print Options** offer you handy features *before* you **Print Labels**. Open the dialog via

- the main menu **File | Label Print Options** *or*
- by clicking on the  button in the main toolbar *or*
- by using the shortcut key **F12**.

Print

- All pages

This is the default. All label pages/QSL cards will be printed.

- Print pages from... to...

If you have a very large, filled print queue, it could be better at times to print only a range of label sheets and continue at another time.

First page

- Start printout at label

It often happens that you have a few labels left on a label sheet and you don't want to waste them (label sheets are expensive). This option lets the printout start at a particular, specified label position you enter here. Take a look at your used label sheet and count all used labels until the first unused label. Start counting in the first column and go down the same column (BV prints first column 1, then column 2 and so on). The first unused label is the one you enter here.

Note: This option is automatically reset after a printout.

Reverse print order

This is useful when you print directly on QSL cards. It is a "last in, first out" function: Z..A is the print order instead of A..Z.

Note: You can always see what you print when you perform a [Print Preview of Labels](#).

See also:

[Print Preview of Labels](#)

[Print Labels](#)

Print Preview of Labels

 Perform the **Print Preview** by going via the main menu **File | Print Preview of Labels** *or* by clicking on the **Print Preview** button *or* by using the shortcut key **Ctrl+R**. You can scroll through all generated print pages.

The print preview is then useful when you are designing or modifying a [Label Layout](#) or when you have set [Label Print Options](#).

See also:

[Label Print Options](#)

[Print Labels](#)

Print Labels

 This is what the program's purpose is all about.

As soon as you have some data in the [Print Queue](#) and the right [Label Layout](#), you are ready for the printout.

Print the Labels or QSL cards by going via

- the main menu **File | Print Labels** *or*
- by clicking on the  button *or*

- by using the shortcut key **Ctrl**+**P**.

Be sure to have set the right printer in the [Printer Setup](#).

The Print Queue is deleted after the printout - either automatically or it has to be deleted manually – depending on the [Configuration - General](#).

Note: BV offers additional [Label Print Options](#) to print just a range of pages, to start the printout at a certain label position or to perform a reverse printout order.

See also:

[Print Preview of Labels](#)

[Label Print Options](#)

Printer Setup

This chapter is not yet available.

See also:

[Print Preview of Labels](#)

[Label Print Options](#)

[Print Labels](#)

Options

Show Print Queue status

 The command **Ctrl**+**Q** shows you information about the print queue and the loaded, active label design in a message box. It gives information about

- how many labels and label sheets (or QSL's) there are in the print queue to be printed,
- how many QSO and footer lines the loaded label layout has *and*
- about the print queue sort order - *alphabetical* or *first in, first out*

The number of labels in the print queue can always be seen in the bottom status bar of the main program window.

- You can click on this information panel to open the print queue information message box *or*
- through the main menu **Options | Print Queue** or
- by clicking on the  button.

See also:

Empty Print Queue

Empty Print Queue

 The command **Ctrl**·**E** empties (deletes) **all** records of the print queue. This command should be used with caution and only used if you have accidentally filled the print queue with wrong records you did not intend to print.

To empty the print queue, use either

- the main menu **Options | Empty Print Queue** *or*
- click on the  button *or*
- use the shortcut key **Ctrl**·**E** *or*
- by typing the key word **EMPTY** into the call sign search field

To delete single, particular entries of the print queue,

- be sure that the print queue window is open - **F10**
- select the record to be deleted by using the cursor keys together with the **Alt** key: **Alt**·**↓** or **Alt**·**↑** and
- delete it by using the key combination **Alt**·**Del**.

There is a context popup menu available on right mouse click when you position your mouse cursor over the print queue window.

See also:

Show Print Queue status

Toggle Log Display Index

 The command **F5** switches between the three available log indexes. The log index determines the sort (display) order of the open log(s). The log can either displayed sorted

- by call signs,
- chronological (sorted by date and time) *or*
- sorted by QSL managers.
According to the used log index, some of the search fields in the search toolbar change.
To switch the log index, use either
- the main menu **Options | Toggle log index** *or*
- click on the "Sort" panel on the left side in the bottom status bar *or*
- use the shortcut key **F5** *or*
- **Shift**·**F5** to toggle back.

When switching from Call index to Date index, the date of the current QSO is taken as default for the date index.

Note: If you have your log in a **chronological order**, and fill the print queue, the print queue is also filled in chronological QSO order and the settings in the configuration are ignored.

See also:

[Search for Call, Band, Mode etc.](#)

Set QSL sent flags

Q5 When the print queue is filled with QSO's from the log, each printed QSO changes its "QSL sent status" in the "QSL sent" column of the log. Which one of the status flags it receives after the print (more exactly: when the QSO is put into the print queue) can be set in the sub menu under:

- the main menu **Options | Set QSL sent marks**

The choices are:

"Y" – "QSL sent"

means: "I have sent a QSL, regardless of whether via the bureau or direct"

"B" – "QSL sent via bureau"

means: "I have sent a QSL via the bureau"

"D" – "QSL sent direct"

means: "I have sent a QSL direct"

"N" – "QSL not sent"

means: "I have not (yet) sent a QSL"

"-" – "No changes"

means: "I don't want the QSL flag to change when I put the QSO into the print queue"

Note: The **QSL sent flag** to be used can also be changed by clicking on the third panel "QSL sent:" in the bottom status bar.

Note: The **QSL sent flags** in the logs can be changed by using the **F8** key.

See also:

[Set QSL received flags](#)

[Toggle QSL sent/received flags](#)

[Filter for QSL sent and received flags](#)

Set QSL received flags

 When the print queue is filled with QSO's from the log, each printed QSO changes its "QSL received status" in the "QSL received" column of the log. Which one of the status flags it receives after the print (more exactly: when the QSO is put into the print queue) can be set in the sub menu under:

- the main menu **Options | Set QSL received marks**

The choices are:

"Y" – "QSL received"

means: "I have received a QSL, regardless of whether via the bureau or direct"

"B" – "QSL received via bureau"

means: "I have received a QSL via the bureau"

"D" – "QSL received direct"

means: "I have received a QSL direct"

"N" – "QSL not received"

means: "I have not (yet) received a QSL"

"-" – "No changes"

means: "I don't want the QSL flag to change when I put the QSO into the print queue"

Note: The **QSL received flag** to be used can also be changed by clicking on the fourth panel "QSL revd:" in the bottom status bar.

Note: The **QSL received flags** in the logs can be changed by using the  key.

See also:

[Set QSL sent flags](#)

[Toggle QSL sent/received flags](#)

[Filter for QSL sent and received flags](#)

Set QSL sent/rcvd date

 **DATE** When the print queue is filled with QSO's, the **QSL sent date** and **QSL received date** columns in the log are filled with a date, which can be entered in this dialog. By default it is the current date. These dates can be set under:

- the main menu **Options | Set QSL sent/rcvd Date** or
- by using the shortcut key .


With the option **No date**, the "QSL sent/received" column is not filled with a date when the print queue is filled.

See also:

[Set QSL sent flags](#)

Set QSL received flags

Answering SWL Cards

 An important feature no other logbook program has – **answering SWL QSL Cards**. First load the SWL label design *sample_swl.bvd* with . Then click on **Options | Answer SWL cards** in BV main window menu. The shortcut key is . A security message will remind you should have a SWL label design loaded. An empty **SWL log grid** will popup.

First, enter the SWL call sign. You can now enter QSO data **manually or** much more comfortably via "**drag and drop**": Search for the QSO records the SWL wants to have confirmed. Perform a log search as you are usually do. Now click on the desired QSO in the log window with the left mouse button (watch how the mouse cursor changes) and *move* the requested QSO from the log window onto the SWL log grid with the mouse. If the QSO can be accepted, the mouse cursor changes it's shape again and you 'drop' it by releasing the left mouse button. That's called "drag and drop" in the Windows language.

When you are finished, click on the **Print** button in the SWL log grid. All data is sent to the print queue. Click on preview  and see how it looks like on the labels.

If you have two or more logs open with different owner call signs, drag and drop onto the SWL log grid is possible only for one **owner call sign** of the logs. This is intended of course. The owner call sign is the right-most column in the SWL log grid. The column has a different color. Once you have placed one owner call sign in the SWL log grid, it cannot be edited anymore. The only chance is to clear all entries by clicking on the **Clear** button.

Note: Use the label layout *sample_swl.bvd* as reference for your own SWL label layouts.

Configuration

Configuration Overview

Important program options can be set or switched off in the **Configuration**.

Open the configuration dialog via the

- main menu **Options | Configuration** *or*
- by clicking on the  Configuration button in the main toolbar *or*
- by using the shortcut key 

The configuration dialog consists of seven tab sheets:

General - to set basic log window options

Combo Boxes - the visible bands and modes in the band and mode combo boxes

Sorting - to choose how multiple QSO's are sorted on the labels

Print Formats - to customize the appearance of fields on the labels

Slashed Zero - how to print zeroes with a slash.

Auto Open Logs - to set the list of logs that will be opened automatically at program start of BV

BDE – shows the BDE configuration

Configuration - General

Confirmation prompt before F2/F3

This option (if checked) prevents you from putting the entire log into the print queue by mistake after pressing **F2** or **F3**. A warning message *Do you want to print all calls?* has to be confirmed then.

Show a continue/discontinue prompt after # labels

This is a "security parameter". The program prompts you to continue or discontinue creating print queue entries after each # labels as defined here. Set the value to 0 if you don't want this prompt.

Clear search fields after **F2** / **F3**

If checked, BV will clear all search fields after putting QSO's into the Print Queue **F2** or **F3**.

Automatically delete Print Queue after printing?

If checked, the print queue will be emptied after every printout of labels. Otherwise a confirmation dialog will appear after each printout, which prompts you to empty the print queue, or not.

Use BV QSL Manager Database

Enable/disable the BV QSL Manager Database.

Note: If you want to save these settings permanently, click on the **Save Changes** button. If you want to set these settings just temporarily, just click on the **OK** button

Configuration - Combo Boxes

Set the visible dropdown list values of the band and mode combo boxes in the log window. If you, for example, don't like to see 2m or FM in the dropdown combo boxes, then uncheck the particular bands and/or modes here.

See also:

[Search for Call, Band, Mode etc.](#)

Configuration - Sorting

Well, now to the difficult part. You have to pay flexibility with some thinking. The settings here and their combinations actually shouldn't leave any wishes and QSL answering habits unfulfilled for multiple QSO with same stations. The decision what to print and how in case of multiple QSO's goes through a complex priority table considering for example if you want to confirm pre-confirmed QSO's again and so on. It's all in all 96 combinations.

Choose QSO's to be printed automatically by these criteria

- **Confirm QSO's again, if previously confirmed**
- **Confirm all QSO's, regardless of the 'QSL Sent' status**

These parameters have the highest priority. If both are checked (means "yes"), BV will print everything what you see in the Log Windows - regardless of already confirmed QSO's or not. Avoid this. By the time you will have a large contest database and it is absolutely unnecessary to confirm previously confirmed QSO's again.

If only **Confirm QSO's again** is checked, BV will print all QSO's of the Log Windows – but ignores those which were already confirmed. Many people prefer this who say "I want to confirm every new QSO that I had" (regardless of multiple QSO's on the same band). The others say: "I have so many QSL's from xxx that I can use them as wallpaper or...". If you belong to this group then continue reading.

- **Confirm only new modes/bands**

At this point BV decides to ignore and drop QSO's according to the **Confirm only new modes** and **Confirm only new bands** settings.

If **Confirm only new bands** and **Confirm only new modes** are checked, the BV printout decision handler will drop all those QSO's with a station on a mode and band that you had confirmed before. Example: BV won't print a QSO with DF3CB on 20m/CW if you already have printed and confirmed a QSO with him before in that band/mode combination 20m/CW.

If **Confirm only new modes** is checked but **Confirm only new bands** not, BV will print all QSO's with in a new mode. Example: You have already printed a QSO with DF3CB on 20/CW but now you worked him on 20/RTTY. BV will print this QSO but it won't print the prior 20/CW QSO because one that is already confirmed.

Vice versa, if **Confirm only new bands** is checked but **Confirm only new modes** not, BV will print all QSO's on new, not yet confirmed bands. Example: You have already printed a QSO with DF3CB on 20/CW but now you have worked him also on 15/CW for the first time. BV will print this QSO. But it will not print the 20/CW QSO.

- **Print first QSO's first and Confirm QSO's again**

One step further. **Print first QSO's first** also decides to possibly drop QSO's *if* you had several QSO's in same band/mode combinations. Either all QSO's are dropped except the last one found (last in, first out), or, the first QSO left and all other following QSO's dropped (first in, first out). This also considers the parameter **Confirm QSO's again**. If this one is not checked and the first QSO was already confirmed in the first in, first out case, the first one will be ignored and it takes the next, not yet confirmed QSO.

The sense and purpose behind this all is to reduce the number of confirmations to the most interesting QSO's on new bands or new modes after having worked KC1XX 372 times in contests.

There are often cases when you don't want to have a computer taking all these decisions and you want to printout specific, single QSO's out of a big choice. Then double-click on the desired QSO(s) in the Log Window. They will be highlighted (marked) then. Afterwards click on the "Marked-QSO's-only" Button in the Search Toolbar that will display only previously marked QSO's and then print.

If you have more than one QSO to print on a label, sort them...

- by bands (160 first, then 80, then 40 and so on...) *or*
- by modes (SSB first, then CW, then RTTY and so on...) *or*
- chronological – sorted by date and time (first QSO's first, last QSO's last)

Sort order of the Print Queue

Two methods are supported depending on the way you want to answer QSL's:

- **First in, first out**

or the direct answering method. The printout is done in the same order as they were entered which means in the same order as the QSL letters were processed.

- **Alphabetical**

or the QSL bureau answering method. The QSL's are printed in alphabetical order .

The sort order can be changed at any time by right-clicking into the Print Queue window and selecting the sort order.

Merge QSOs in print queue and/or from different logs into one label

This option is set by default. If you have a QSO for e.g. DF3CB in the print queue and if you add another QSO for DF3CB later, this additional QSO is also put on the same label then if there are still free QSO lines left. If there are no free QSO lines left, a new label is started. If this option is not checked, every additional QSO will automatically be printed on a new label.

Configuration - Print Formats

Set the appearance of QSO information as it is printed on the labels here (this does not apply to the log display in the Log Windows).

Date Format

The date display format can be customized to your personal favored style. You enter a "format string" in the Date Display Format edit field consisting of various parameters. First decide upon the order of day, month and year display.

Let's say you want a display like '2000-Dec-31'. So, year is first and type four times the letter *y* ("y" for "year"). *yy* displays the year with two digits ("00"). *yyyy* displays the year with four digits ("2000"). It is recommendable to use separators between the date elements. As you type the characters the results are immediately visible in the preview panels. Now type a dash ("-"), followed by three times the letter *m* ("m" for "month"). The display now changes to "2000-Dec" (in fact, the current date is used there).

m displays the month as a number without a leading zero (for January to September), *mm* the month as a number with a leading zero, *mmm* the month as an abbreviation (Jan-Dec), *mmmm* the month as a full name (January – December). Now again another separator dash followed by the day designator *d*. Type twice the letter *d*. The display now shows "2000-Dec-31". *d* displays the day as a number without a leading zero (for the first nine days of a month), *dd* the day as a number with a leading zero, *ddd* the day as an abbreviation (Sun-Sat), *dddd* the day as a full name (Sunday – Saturday).

The Date Format may differ from the Date Display Format of the Log Windows.

Time Format

Next we have the **Time Format**. It can either be set to five digits a separator (e.g. 23:59) or four digits without a separator (e.g. 2359).

Band Format

Accordingly to the **Band Format**, bands will either be printed as wavelength in meters (like 160m, 80m, 40m ...) or as frequency in MHz (like 1.8, 3.5, 7).

PSE/TNX flags

If a QSL wasn't received yet (QSL received = N) you can print a short PSE text in each QSO line. Otherwise a TNX text is printed. The texts can be set here (up to 6 characters).

Manager text

If you print QSL manager information on the QSL, you can precede a text, which is usually "via:".

Configuration - Slashed Zero

Call signs should be printed with slashed zeroes ('Ø') instead of a usual zero ('0') to better distinguish between the number 0 (zero) and the character O. The default ASCII Code for Ø is 0216. This default can be changed to another ASCII code, which complies with your selected font. Enter a language-dependent ASCII code for the slashed zero. Common ASCII codes are proposed in the drop-down list (216, 232, 248).

Configuration - Auto Open Logs

Up to 32 logs can automatically be opened at BV program start. All logs in the right hand list box on the tab folder "Auto Open Logs" will be opened then. Click on the logs in the left box, then click on the arrow buttons to move them into the right box.

Click on the **Save Changes** Button afterwards to make your list available for the next BV program session.

Configuration - BDE

This tab sheet is just for information purposes and displays the BDE (Borland Database Engine) settings. BV sets them automatically.

Search

Search for Call, Band, Mode etc.


 The normal procedure to answer incoming QSL cards is to enter the call sign in the call sign field of the search toolbar and, if found, to press **F2** to put the QSO(s) into the print queue and to later print it. It can happen that you don't find a particular call sign in the log or that you want to QSO's particular bands or ranges or call signs. For these cases you need to extend the log searches by using additional selections (or filters).

Filters can be applied to the log on call signs, date and time, bands, modes and QSL managers plus other filters for QSL sent and received flags or marked QSO's.

BV uses an incremental log search method. This means that the log search is performed after every keystroke or change of the combo box values - in all open logs. Therefore you see your search results immediately.

Call sign search

Begin to enter a call sign you can see in the log, e.g. DL1IAO, into the left search field of the search toolbar. Use the **Esc** key to enter this field or the shortcut key **Alt+C** or click into the field.



The image shows a search toolbar with four main sections: 'Call Search', 'Call Range', 'Band', and 'Mode'. The 'Call Search' field contains the text 'DL1I'. The 'Call Range' field is empty. The 'Band' field has a dropdown arrow pointing down. The 'Mode' field has a dropdown arrow pointing down.

While you enter the call sign, the incremental search mechanism tries to find the first QSO record that matches with the entered search values and displays a range of the log. As soon as there is an **exact (call sign) match**, only the QSO's for the particular match are displayed.

Note: Use the **Tab** key or **Enter** key to jump to all other input fields

Note: All search fields can be cleared by pressing the function key **F11**.

Call sign range search

Optionally, a second call sign or prefix can be entered in the second call sign search field for **call sign range searches**. This is useful to limit the search results or to print particular prefix ranges. Note that, due to the alphabetical character order, the prefix in this field has to be "greater" than in the first call search field. Otherwise there will be no results. The shortcut key to enter this field is **Alt-L**.

Filter for bands

You can filter the log for particular bands by choosing a band from the **Band combo box**. The shortcut key to enter this field is **Alt-B**. The visible values of this combo box can be defined in the **Configuration - Combo Boxes**. Hint:: typing the first figure of the band, e.g. "2" for "20m", displays the band immediately and is faster than popping up the drop down list and then choosing a band.

Filter for modes

You can also filter the log for particular modes by choosing a mode from the **Mode combo box**. The shortcut key to enter this field is **Alt-M**. The visible values of this combo box can be defined in the **Configuration - Combo Boxes**. Hint:: typing the first character of the mode, e.g. "S" for "SSB", displays the mode immediately and is faster than popping up the drop down list and then choosing a mode.

Searching for date and time

To search the log for a specific date and time, you need to switch the log index to the chronological index. The function key **F5** toggles the log index between display sorted

- by call signs,
- by date and time (chronological) and
- by QSL managers

Using the chronological index, the date and time search fields become visible.

Date search

Date search is useful to find QSO's in the logs, which were probably, logged wrong. Enter a specific date in the format *yyyy.mm.dd* and watch the log display change. The shortcut key to enter this field is **Alt-D**. For large logs, enter also a (start) time in the format *hhmm* in the next field – the time field. The shortcut key to enter this field is **Alt-T**.

Date range search

Optionally, a second date can be entered in the second date (and time) search field for **date range searches**. This is useful to limit the search results or to print particular date ranges. The shortcut key to enter this field is **Alt-E**. Note that, due to the ascending sort order, the date in this field has to be "greater" than in the first date search field. Otherwise there will be no results. The same applies to the second time field. The shortcut key to enter this field is **Alt-J**.

Searching for managers in the log

Using the third log index – the manager index - the QSL manager field becomes visible. The shortcut key to enter this field is **Alt-G**. The prerequisite is that your log contains QSL manager information.

See also

[Toggle Log Display Index](#)

[Filter for QSL sent and received flags](#)

[Filter marked QSO's](#)

Filter for QSL sent and received flags

When the print queue is filled with QSO's from the log, each printed QSO changes its "QSL sent" and "QSL received" status in the **QSL sent/rcvd** columns of the log.

The possible values are:

"Y" – "QSL sent/received"

means: "I have sent/received a QSL, regardless of whether via the bureau or direct"

"B" – "QSL sent/received via bureau"

means: "I have sent/received a QSL via the bureau"

"D" – "QSL sent/received direct"

means: "I have sent/received a QSL direct"

"N" – "QSL not sent/received"

means: "I have not (yet) sent/received a QSL"

"!" – "Will never send or receive a QSL"









means: "I don't expect to receive a QSL and/or will never send a QSL"

The log can be filtered for these flags through the sub menu

 the main menu **Search | QSL sent flag** or

 the main menu **Search | QSL received flag**

or by using these shortcut keys:

	 QSL sent
	 QSL not yet sent
	 QSL sent via bureau
	 QSL sent direct
	 will never send a QSL
	 QSL received
	 QSL not yet received
	 QSL received via bureau

-   QSL received direct
-   will never receive a QSL

Use the sub menu item  **No filter** to reset the QSL sent/rcvd filters or  to reset all search conditions.

Note: The **QSL sent flags** in the logs can be changed by using the  key and the **QSL received flags** by using the  key.

See also:

[Set QSL sent flags and Set QSL received flags](#)

[Toggle QSL sent/received flags](#)

[Wipe search fields](#)

Filter marked QSO's

- Use the function key  to filter the log for **Mark QSO's**. This is a toggle function.

See also:

[Mark QSO](#)

[Remove all QSO Marks](#)

Wipe search fields

 The key  clears all search fields and filters and resets the log so that you see the entire log again. The **configuration** can be set so that the search fields and filters are automatically cleared after every action of filling the print queue.

See also:


[Search for Call, Band, Mode etc.](#)

Log

Log Navigation

You can easily navigate through the log by using the cursor keys:

-   Move to next QSO record

-  Move to prior QSO record
-  Move 10 QSO's forward
-  Move 10 QSO's backward
-  Move to last QSO record
-  Move to first QSO record

See also:

[Selecting QSO records](#)

[Search for Call, Band, Mode etc.](#)

Selecting QSO records

The user can select multiple, non-contiguous rows by keeping the  key pressed and clicking on any QSO rows. To select contiguous rows, keep the  key pressed and use the  or  keys. If you have chosen a multiple selection, only these selected QSO's will be printed. The number of selected records will appear in the status bar of the active log window.

See also

[Log Navigation](#)

[Select row down](#)

[Select row up](#)

[Select all QSO's of this Call](#)

[Unselect](#)

[Fill Print Queue with selected QSO's](#)

Select row down

 Use the shortcut key   to select contiguous rows in the log for selection purposes.

See also

[Log Navigation](#)

[Selecting QSO records](#)

[Select row up](#)

[Select all QSO's of this Call](#)

[Unselect](#)

[Fill Print Queue with selected QSO's](#)

Select row up

 Use the shortcut key **Shift**+**↑** to select contiguous rows in the log for selection purposes.

See also

[Log Navigation](#)

[Selecting QSO records](#)

[Select row down](#)

[Select all QSO's of this Call](#)

[Unselect](#)

[Fill Print Queue with selected QSO's](#)

Select all QSO's of this Call

 Use the shortcut key **Ctrl**+**A** to select all QSO's in the log for one particular call sign if there is more than one QSO listed. This is useful if you want to print all QSO's for this call sign.

Then use the shortcut key **Ctrl**+**←** to [fill the print queue with these selected QSO's](#) or press **F2**.

Press **Esc** to [unselect](#) (cancel) this selection.

See also

[Log Navigation](#)

[Selecting QSO records](#)

[Select row up](#)

[Select row down](#)

[Unselect](#)

[Fill Print Queue with selected QSO's](#)

Unselect

 A [selection](#) can always be cancelled by pressing the **Esc** key or by clicking on the select counter in the top panel of the active log.

See also

[Log Navigation](#)

Selecting QSO records

Select row up

Select row down

Select all QSO's of this Call

Fill Print Queue with selected QSO's

Fill Print Queue with selected QSO's

 Use the shortcut key `Ctrl+P` to fill the print queue with either one QSO, if only one QSO is selected, or with all selected QSO records, if several are selected. In comparison to `F2`, only selected QSO records are put into the print queue instead of probably the whole log.

See also

[Fill the Print Queue](#)

[Selecting QSO records](#)

[Select row up](#)

[Select row down](#)

[Select all QSO's of this Call](#)

[Unselect](#)

Fill QSO Record(s) with QSL Manager

 Use the shortcut key `Ctrl+F` to fill the manager field in the log from the QSL manager database. You can alternatively drag and drop the manager from the manager edit field into your log or open the popup manager list right to the manager edit field and click on the right manager. If you have selected several QSO's, all records are filled with the manager.

See also

[QSL Manager Database](#)

[Fill entire log with QSL Managers](#)

Fill entire log with QSL Managers

 You can fill the entire log with QSL Managers from the BV QSL manager database now if you cannot import your manager information through the log import. Use the "Fill entire log with QSL Managers" command in the **Log** menu. This automatic function tries to fill only those QSO's that don't have a manager yet. It can be aborted at any time by pressing the `Esc` key.

See also

[QSL Manager Database](#)

Fill QSO Record(s) with QSL Manager

Mark QSO

 Double-click on particular QSO records in the log window to **mark** them - they will be highlighted in red then. The alternative is the shortcut key **Alt-F7**. Marking QSO's is useful if you want to print only particular QSO's, for example you had 348 QSO's with K3LR in contests and you want to confirm only two of them.

In comparison to *selections*, marked QSO's remain marked until they are put into the print queue or until the mark is removed. The marks are even kept when you close the log and open it again later.

Remove single marks

A mark is removed automatically when a QSO is put into the print queue. A mark can be removed manually

- by double-clicking again on the marked QSO record,
- by using **Alt-F7** again over already marked QSO records

Remove all marks

All QSO marks in the active log are **removed** after using the shortcut key **Ctrl-F7**.

Filter marked QSOs

Use the function key **F7** to **filter the log for marked QSOs**.

See also:

[Filter marked QSO's](#)

[Remove all QSO Marks](#)

[Selecting QSO records](#)

Remove all QSO Marks

 All QSO marks in the active log can be removed by using the shortcut key **Ctrl-F7**.

See also

[Mark QSO](#)

[Filter marked QSO's](#)

Toggle QSL sent/received flags

The QSL sent and received flags are explained in the chapter [Filter for QSL sent and received flags](#).

 Use the shortcut key **F8** to **change the QSL sent status manually** for the QSL sent flag. **F8** will toggle the status back and forth.

Qr Use the shortcut key **F9** to **change the QSL received status manually** for the QSL received flag. **F9** will toggle the status back and forth.

Changing QSL flags in a bulk mode

With a multiple selection active, **F8** and **F9** will change the **QSL sent** and **QSL rcvd flags** all together in a bulk mode.

Note: Changing the QSL sent and received flags (F8/F9), sets also the QSL sent and received date. Setting the flags to "N" or "!", empties the QSL sent and received date.

See also:

[Set QSL sent flags and Set QSL received flags](#)

[Filter for QSL sent and received flags](#)

Log Statistics

 Open the **Log Statistics** via

- the main menu **Log | Log Statistics** *or*
- by clicking on the  button in the log *or*
- by using the shortcut key **Shift** · **Ctrl** · **S**.

The Log Statistics calculate

- how many QSO's you had on each band and mode,
- how many QSO's were already confirmed and
- how many labels you will need for printing the remaining, not yet confirmed QSO's.

The *amount of labels needed* depends of course on the number of QSO and footer lines in the currently loaded label layout. Naturally you need many more labels with three QSO lines per label than with six QSO lines per label. The algorithm behind this considers all [configuration settings](#) as well.

Note: All calculated results are based on the search and filter criteria you have entered in the search toolbar. Clear all selected criteria with **F11** to see the statistics for the *entire* log.

Footer Lines

 You can *optionally* print **Footer Lines** on your labels. Footer lines are usually different from log to log – that's why they "belong" to one log. Therefore the footer lines have to be registered for each new BV log. How many footer lines you enter depends on how many footer lines you will and can print in the label layout. The maximum is nine lines. It does not make sense to enter more than one footer line if your label layout has only one footer line.

Open the **Footer Lines** form via

- the main menu **Log | Footer Lines** *or*
- by clicking on the  button in the log *or*
- by using the shortcut key **Shift** · **Ctrl** · **F**.

Enter the log-specific footer lines line by line. They can be saved as default and this default can be made available for other logs then after opening this footer lines form for other logs.

Log Grid Setup



You can customize the appearance of the logs (log grids) with the help of the **Log Grid Setup**.

Open the **Log Grid Setup** form via

- the main menu **Log | Log Grid Setup** *or*
- by using the shortcut key **Shift** + **Ctrl** + **G**.

The form contains two tab folders – the *Display* and the *Columns* tab.

Display Tab

There are two predefined settings,

- the *Default* and
- *DF3CB's favorite*

which can be selected **Predefined Settings** combo box. As soon as you change any of the settings, the program saves these settings as *User settings*.

You can choose a **Background Color** for the log grid, check whether you want to see **Column Titles**, an **Indicator** on the left-hand side of the grid, **Column Lines** between the grid columns and **Row Lines** between the grid rows.

The **Date Display Format** of the date columns (Date, Date QSL sent, Date QSL rcvd) can be set here too.

The date display format can be customized to your personal favored style. You enter a "format string" in the Date Display Format edit field consisting of various parameters. First decide upon the order of day, month and year display.

Let's say you want a display like '2000-Dec-31'. So, year is first and type four times the letter *y* ("y" for "year"). *yy* displays the year with two digits ("00"). *yyyy* displays the year with four digits ("2000"). It is recommended to use separators between the date elements. As you type the characters the results are immediately visible in the preview panels. Now type a dash ("-"), followed by three times the letter *m* ("m" for "month"). The display now changes to "2000-Dec" (in fact, the current date is used there).

m displays the month as a number without a leading zero (for January to September), *mm* the month as a number with a leading zero, *mmm* the month as an abbreviation (Jan-Dec), *mmmm* the month as a full name (January – December). Now again another separator dash followed by the day designator *d*. Type twice the letter *d*. The display now shows "2000-Dec-31". *d* displays the day as a number without a leading zero (for the first nine days of a month), *dd* the day as a number with a leading zero, *ddd* the day as an abbreviation (Sun-Sat), *dddd* the day as a full name (Sunday – Saturday).

Note: The date format here may differ from the date display format of the printed labels.

Columns Tab

Every single column in the log grid can be completely customized here. The checklist box on the left-hand side of the Columns tab lists all available log columns (fields). If you don't want to have some of these columns visible, simply uncheck the particular column names in the list box.

The order of the columns can be changed by dragging the column name (hold the left mouse button pressed), moving it to another position and dropping it (release the left mouse button).

Note: It is recommended to uncheck the Sub-Mode column.

Display properties of the single columns can be changed *after* clicking on the column names in the column name list box.

The **Title Caption** (title means the first grid row or header of the grid) can be set as well as the **Width** of the column, measured in characters, the **Title Alignment** (left, right, center), the title row **Background** color and **Font**. If you check the **Apply to all Columns** checkboxes, all changes will be applied to *all* columns.

You may want other colors for the data rows of the grid. Set the **Data Alignment**, **Data Background** color and **Data Font** accordingly.

After clicking on the OK button, all made changes will be saved and applied to all open logs.

Windows

Label Designer

 The **Label Designer Window** is the second main BV program window. Open it via

- the main menu **Windows | Label Designer** *or*
- by clicking on the  button in the main toolbar *or*
- by using the shortcut key **Ctrl+D**.

The BV Label Designer is described in the separate, large chapter **Label Designer**.

Tools (Import/Export)

 The **Tools Window** of BV is the **Log Conversion** part of the program (import/export of logs). Open it via

- the main menu **Windows | Tools (Export/Import)** *or*
- by clicking on the  button in the main toolbar *or*
- by using the shortcut key **Ctrl+T**.

See the chapter **BV Tools** for a complete description.

QSL Manager Database

 The **Manager Window** of BV allows you to import and maintain a **QSL Manager Database**. Open it via

- the main menu **Windows | QSL Manager Database** *or*
- by using the shortcut key **Ctrl+M**.

See the chapter **QSL Manager Database** for a complete description.

QSO Edit Window

To **edit wrong QSO data**, switch the log into **Edit Mode**. The shortcut keys for changing the mode and opening the QSO Edit window is **F4** (toggle function) or choose the **Windows | QSO Edit Window** item from the main menu.

Move the QSO Edit window to a convenient place - the window stays on top of the application. The window position will be stored.

- Changes will immediately be applied to the log as soon as you hit the **↓** or **↑** keys or any other of the navigation keys, e.g. **Page Down** or **Page Up**.
- Click on the **Insert** button to *add new QSO's* to the log.
- Click on the **Delete** button to *remove QSO's* from the log.
- Hit **F4** again to close the QSO Edit window.

Print Queue Window

The **Print Queue Window** can be made visible by pressing the function key **F10** (toggle function) or when you choose the **Windows | Print Queue Window** item from the main menu.

The Print Queue Window lists all entries which were put into the print queue by the various methods, e.g. **F2** or **Ctrl+←**. When you hold the mouse over the Print Queue Window, a hint appears with raw QSO information.

To navigate in the Print Queue Window, use the **Alt** key together with the cursor keys. To delete single entries from the print queue, use the key combination **Alt+Del**. A context popup menu with all available choices is opened if you right-click over the Print Queue Window.

The Print Queue has two sort orders (indexes), one is the alphabetical index, the other the FIFO index (first in first out). The index and, at the same time, the display order, can be changed at any time. The alphabetical index is recommended if you answer and print bureau QSL cards, the FIFO index when you process direct QSL requests.

See also:

[Fill the Print Queue](#)

[Fill Print Queue with selected QSO's](#)

[Show Print Queue status](#)

[Empty Print Queue](#)

Jumping between Log Windows

If you have more than one log open, use either the **Window Menu**, the Log Window title bars, click on the  or  buttons or use the shortcut keys **F6**, **Shift+F6** or **Ctrl+F6** to jump between the open logs.

Arranging the Log Windows

All open log windows can be **maximized**, **cascaded** or **tiled** within the main BV program window. Only one log can be active at one time while all log search actions are performed on all logs - one after the other. If you click on the Maximize icon in one of the logs, all logs are maximized while only the active log is visible. Even then, all log search actions are performed on all logs.



Shift·**Ctrl**·**C** Cascade all log windows



Shift·**Ctrl**·**H** Tile all log windows horizontally



Shift·**Ctrl**·**V** Cascade all log windows vertically



Shift·**Ctrl**·**M** Maximize all log windows

Reset all Dock Positions

All toolbars can be dragged and docked to other positions in the program screen or outside of the program screen. If you get stuck or "loose" accidentally toolbars, click on this menu item to reset all toolbars to its default positions.

Help

BV Label Designer

Label Designer Introduction

The BV QSL Label Designer is a graphical tool to design the layout of the QSL labels you want to print or the layout of what you want to print directly on your QSL cards.

[Opening the Label Designer Window](#)

The BV QSL Label Designer is the second main program window of the application. Open it by

- clicking on the window or
- via the main menu [Windows | Label Designer](#) or
- by clicking on the **Label Designer** button or
- by using the shortcut key **Ctrl**·**D**.

[Layout Elements](#)

Have a look at the window. It consists of a design canvas and several toolbars. The BV installation contains two sample layouts. The sample layout *sample.bvd* is automatically loaded when you start BV the first time.

The design canvas contains several elements. The basic element is the **Page**. Its color is a light yellow and it has design grid lines as well as a ruler on top of the panel. The page represents the label sheet or QSL card you later print on. The dimensions are defined in the [Layout settings](#).

The white area is the **QSL Label** itself or also called the printable area. The actual design is done only once, it is automatically duplicated at print time for the rest of the labels on a page.

The elements on the QSL Label area are either [Data Fields](#), [Text Elements](#), [Expressions](#), [Memo Fields](#), [Shapes](#) or [Images](#). Each element is marked on the edges, if you click on one, and has a certain function, position and properties.

Click on any of the elements in the layout and watch the status bar on the bottom of the window change.



It shows information about the element type, its exact position either in millimeters, inch or pixel, its width and height, how many QSO lines and footer lines the layout contains and whether the layout was modified or not. The units are defined in the [Basic Options](#) dialog.

Next steps

After you have had a look to the [Basic Options](#), read the next chapter [Handling Elements](#).

You should then get familiar with the [Layout Elements](#) in particular before you proceed to modify basic [Layout Settings](#) or to [Create New Layouts](#).

Basic Designer Window Options

 Set your basic designer window options in the BV Designer Label Options dialog. The most important one is to set the unit.

Units

This is the unit that the layout designer uses for measuring and drawing of the ruler and grid lines. Millimeter, Inch and Characters are available.

Design Grid

Activate this option to show grid lines when editing the layout. These lines make it easier to move and align layout elements.

Automatically align elements to grid

Grid size

This sets the (invisible) grid to which layout elements are aligned automatically. You can use it for easier alignment of layout elements to the same horizontal or vertical position. Note: You can move a layout element by one pixel even if a bigger grid size is set if you hold down the **[Shift]** key while moving the element.

Keyboard grid size

Same as "Grid size", but for keyboard movement with the cursor keys instead of the mouse.

Frames

Show component frames at design time

If this option is activated frames will be drawn around each layout element at design time. This way layout elements can be displayed more distinctly. The frames are only drawn in design mode, not during printout.

Color

Choose a convenient color for the element frames.

Line

Frame style, either solid, dashed or dotted.

All settings will be applied and saved after clicking on the **OK** button.

Next steps

Handling Elements.

Handling Elements

Editing layout elements

The individual **properties** of a layout element can be changed anytime during layout design. Select the desired element and either double-click with the left mouse button, or press the right mouse button and choose "Properties" from the popup menu. The property dialog for the selected layout element will open, which is the same dialog as the one that shows up when inserting a new layout element. Edit the element properties to your needs and press the "OK" button to close the dialog and accept your changes. If you press "Cancel", all your changes are dropped and if you were inserting a new element, it will not be added to the layout.

Information about the different properties for each layout element can be found at the individual element descriptions.

Toolbar

You can change many layout element properties directly with the toolbar instead of using the element's property dialog. Additionally you can use it to modify multiple elements at once.



These buttons are used for creating a new layout, for loading a layout file and saving a layout.



Use these buttons to view a preview of the printout and to print the layout.



With these buttons layout elements can be cut to, copied to or pasted from the layout designer's clipboard.



These buttons are used to set a layout element to the background or bring it in front of all other layout elements, in case of overlapping elements.



Layout elements can be arranged with this buttons. Some of the buttons are only enabled when multiple elements are selected (for example to align the left edges).

This part of the toolbar shows the type of the currently selected layout element and its main property (text if it is a label, data field, band type, ...). You can edit this property directly with the toolbar, without the need to open the element's property dialog.



Here you can set font and font styles of the selected layout elements (font name, font size, bold, underline, italic).



These buttons are for aligning text within a layout element. Text can be aligned left, right or centered. Of course this only makes sense if the layout element's size is bigger than its text, and if "auto size" is deactivated.



With this button you can open a dialog to set the frame options for the selected element.

Using the mouse

- Select a layout element

Layout elements are selected by clicking them with the left mouse button. A selection is shown with eight small black boxes around the element:



- Change the size of an element

You can use the small boxes of a selected element to change its size. If the mouse cursor is positioned over such a box, the cursor will change to show in which direction the mouse can be moved while the left mouse button is pressed down. The element will be resized accordingly. Please note that for layout bands only the height can be changed, but the width is set to the layout width automatically.

- Select multiple elements (a)

You can select multiple elements by holding down the **Shift** key while selecting them with the left mouse button. This way the previous selection will remain when a new element is selected.



- Select multiple elements (b)

You can also select multiple elements by using a so-called "rubber band". Hold down **Ctrl** together with the left mouse button and drag a frame around the elements that you want to select. After releasing the mouse button all elements within the frame are selected.

- Move elements

You can move layout elements with the left mouse button. Hold down the button, drag the element to the desired location and release the mouse button. Layout bands cannot be moved because they are positioned automatically according to their band type.

- Move and resize elements regardless of the current grid setting

If you want to manipulate a layout element regardless of the current grid (menu item "View | Options") and move or resize by one pixel, then hold down the **[Shift]** key while moving the mouse.

- Edit element properties

If you double-click a layout element with the left mouse button, or if you select "Edit" from the element's popup menu (which can be accessed with the right button), a dialog will be shown where all element properties can be edited.

Using the keyboard

The layout designer can be used with the mouse most of the time. Some functions can also be accessed with the keyboard:

- **Enter**

Show the element's property form

- **Cursor keys**

Move a layout element

Shift + Cursor keys

Resize a layout element

- **Del**

Delete a layout element

- **Tab and Shift + Tab**

Select next or previous layout element

Layout Elements

The elements on the QSL Label area are data fields, text elements, expressions, memo fields, shapes or images. Each element is marked on the edges, has a certain function, position and attributes. Buttons for adding layout elements to the layout can be found on the left side of the designer window.

To add an element to the layout you must click its button and then click on the layout where you want the element to be inserted. Of course you can still move a layout element to another position later.

The individual attributes (properties) of a layout element can be changed anytime during layout design. Select the desired element and either double-click with the left mouse button, or press the right mouse button and choose "Properties" from the popup menu. The property dialog for the selected layout element will open.

Edit the element properties to your needs and press the **OK** button to close the dialog and accept your changes. If you press **Cancel**, all your changes are dropped and if you were inserting a new element, it will not be added to the layout.

Information about the different properties for each layout element can be found at the individual element descriptions:

See also:



Data fields



Text elements



Expressions



Creating New Layouts

 If you want to create a completely new layout instead of modifying an existing one, call the **New Layout Definition Wizard**. To modify an existing, loaded label design, call the **Layout Settings** instead (the **Layout Settings** can always be called). It is basically the same except that it does not have the tab folder to choose between the design types "Print on QSL labels" and "Print on QSL cards".

Open the **New Layout Definition Wizard** via the

- Main Menu **File | New...** *or*
- by clicking on the  button in the main toolbar *or*
- by using the shortcut key **Ctrl+N**

The first tab folder **New Layout** let's you choose between the design types

- **Print on QSL labels** and
- **Print on QSL cards**.

Select one of the types and then click on the **Next** button to select a **Label Type**.

Modifying a Label Layout

Follow these steps to create a customized label layout, which meets your needs.

- 1) Open the Designer Window and start the **Layout Wizard** with **Ctrl+N**.
- 2) Choose one of the types **Print on QSL labels** or **Print on QSL cards**.
- 3) If you choose **Print on QSL cards**, you will design a **Custom Type Format** with the dimensions of your QSL card.
- 4) If you choose **Print on QSL labels**, you can either design a **Custom Type Format** *or* choose a **Standard Type Format**. If you click on the Standard Type format, you have the choice of 31 different label suppliers and 1490 predefined label formats. Choose the product you use and click on "Next".
- 5) Check the page values and click again on "Next". Define how many QSO lines you want to have on the label (or QSL) and check "Create layout template" before clicking on "Finish".
- 6) BV then creates a template with basic fields according to the previously defined settings. You can't expect more comfort!

Save the layout under a new name and arrange the fields in the layout by clicking on the particular [Layout Elements](#) and moving them to the right place with the mouse or with the cursor keys.

Label Designer Command Overview

File and Print Commands

	Ctrl + N	Create a new label design
	Ctrl + L	Load label design
	Ctrl + S	Save label design
	Ctrl + Shift + S	Save label design as...
	Ctrl + T	Basic Designer Window Options
	F12	Label Print Options
	Ctrl + P	Print Labels
	Ctrl + R	Print Preview of Labels
		Printer Setup
	Alt + X	Back to log window

Edit

	Ctrl + Z	Undo last action
	Ctrl + X	Cut
	Ctrl + C	Copy
	Ctrl + V	Paste
	Ctrl + Del	Delete
		Send to back
		Bring to front

View

		Zoom to default size
	Ctrl + +	Increase zoom



Ctrl+[-]

Decrease zoom

Layout



Ctrl+Y

Layout Settings



Ctrl+A

Add missing fields automatically



Ctrl+J

Adjust all QSO and footer lines



Ctrl+E

Analyze layout settings



Ctrl+K

Create layout template

Help Commands



F1

Help about BV label designer

Label Frame Properties



Frames can be drawn around each layout element. This way layout elements can be displayed more distinctly.

Layout Elements

Data Fields



A data field displays QSO data from the Print Queue table.

The following options are available:

Data field

Select the data field you want to print.

Alignment

The element's text can be aligned left, right or centered.

Format

Setting a format definition can format numerical data fields.

Font

Selects the font for the element

Color

Defines the background color for the element (the font color can be set with the "Font" button).

Automatic word-wrap

Set this option if you want the text to wrap to the next line if it does not fit into the given width (similar to a word processor software).

Transparent

The element's background will not be printed if this option is activated. This way you can place text on top of an image for example, without hiding the image under a white box with text.

Autosize width

This option resizes the element to make room for its complete text. If "Autosize" is not set and the text is larger than the element size then text will be clipped off.

Autostretch height

This option is for elements with multiple lines, e.g. memo fields. The height of the elements will be stretched to make room for all lines. If needed, the band will be stretched too.

See also:

 Text elements

 Expressions

 Memo fields

 Shapes

 Images

Text Elements

 A text element is for printing static text, i.e. text that is printed exactly like it is displayed during layout design.

The following options are available:

Caption

This is the text that should be printed. You can only type in one line of text. **Memos** can be used for multi-line text.

Properties

- Font

Selects the font for the layout element

- Alignment

The layout element's text can be aligned left, right or centered.

- Automatic word-wrap

Set this option if you want the text to wrap to the next line if it does not fit into the given width (similar to a word processor software).

- Transparent

The layout element's background will not be printed if this option is activated. This way you can place text on top of an image for example, without hiding the image under a white box with text.

- Autosize width

This option resizes the layout element to make room for its complete text. If "Autosize" is not set and the text is larger than the element size, text will be clipped off.

- Autostretch height

This option is for layout elements with multiple lines, e.g. memo fields. The height of the elements will be stretched to make room for all lines.

- Backgr. Color

Defines the background color for the layout element (the font color can be set with the "Font" button).

- Rotation

Use this to rotate your text. Rotation can be set to anything between 0 and 360 degrees. 90-degree means displaying the text vertically for example.

See also:

 Data fields

 Expressions

 Memo fields

 Shapes

 Images

Expressions

 A calculated field (expression field) is used for displaying text or data that is calculated by an expression or formula. You can do string manipulations, concatenate data fields and much more.

Expression

Expressions are usually combinations of print queue data fields and text.

Examples:

MYCALL+' confirms the following QSO(s):'

The static text ' **confirms the following QSO(s):**' is added behind the print queue data field **MYCALL** that is the field for the call sign of the QSO partner. There are shorter and longer calls and this expression helps to print the static text directly behind the field with just ones space. This looks nicer than a large gap between the call sign and the text.

COPY(A_DATE, 1, 4)

This expression is used if you print on QSL cards with separate boxes for year, month and day. Be sure to set the date format to be printed to **yyymmdd**. See the [Configuration - Print Formats](#) chapter. At print time, this expression takes the first 4 numbers (the year) and prints it. The expression for extracting the month is:

COPY(A_DATE, 5, 2)

And for the day:

COPY(A_DATE, 7, 2)

- Fieldname

This is the print queue field list for lookup purposes.

- Validate

Validate your expression by clicking on this button.

Properties

- Font

Selects the font for the layout element

- Alignment

The layout element's text can be aligned left, right or centered.

- Automatic word-wrap

Set this option if you want the text to wrap to the next line if it does not fit into the given width (similar to a word processor software).

- Transparent

The layout element's background will not be printed if this option is activated. This way you can place text on top of an image for example, without hiding the image under a white box with text.

- Autosize width

This option resizes the layout element to make room for its complete text. If "Autosize" is not set and the text is larger than the element size, text will be clipped off.

- Autostretch height

This option is for layout elements with multiple lines, e.g. memo fields. The height of the elements will be stretched to make room for all lines.

- Backgr. Color

Defines the background color for the layout element (the font color can be set with the "Font" button).

- Rotation

Use this to rotate your text. Rotation can be set to anything between 0 and 360 degrees. 90-degree means displaying the text vertically for example.

See also:



Data fields



Text elements



Memo fields



Shapes



Images

Memo Fields



A memo is used to print text that has more than one line. Just like a [text field](#), a memo displays text in one color and font.

The following options are available:

Memo lines

This is the text that will be printed.

Properties

- Font

Selects the font for the layout element

- Alignment

The layout element's text can be aligned left, right or centered.

- Automatic word-wrap

Set this option if you want the text to wrap to the next line if it does not fit into the given width (similar to a word processor software).

- Autosize width

This option resizes the layout element to make room for its complete text. If "Autosize" is not set and the text is larger than the element size, text will be clipped off.

- Autostretch height

This option is for layout elements with multiple lines, e.g. memo fields. The height of the elements will be stretched to make room for all lines.

- Backgr. Color

Defines the background color for the layout element (the font color can be set with the "Font" button).

See also:



Shapes



This layout element can be used to draw (horizontal or vertical) lines, circles and rectangles.

The following options are available:

Type

Selects the shape, which can be a circle, rectangle, horizontal line, vertical line or top/bottom and left/right lines.

Brush

Style: different styles to fill a circle or rectangle

Color: the color that is used to fill the shape

Pen:

Width: line width of the shape

Mode: various line drawing modes

Style: solid, dotted or dashed lines

See also:



Images



An image element is a bitmap from a file that is inserted into the layout. It can be bitmaps (*.bmp), JPEG files (*.jpg), WMF files (*.wmf), EMF files (*.emf) or icons (*.ico).

Filename

Enter the filename for the image or click on the browse button ('...') to select one.

Stretch pictures

Check this option to stretch the image in a previously defined canvas area (height and width).

Center picture

Check this option to center the image in a previously defined canvas area (height and width).

See also:



Data fields



Text elements



Expressions



Memo fields



Shapes

Layout Settings

Layout Settings

 Call the **Layout Settings** dialog if you want to modify or customize an **existing label layout**, e.g. the sample layout *sample.bvd*. If you want to create a completely new layout, call the **New Layout Definition Wizard** instead. It is basically the same except that it has one more tab folder to choose between the design types "Print on QSL labels" and "Print on QSL cards".

Open the dialog via the

- Main Menu **Layout | Layout settings** *or*
- by clicking on the  button in the main toolbar *or*
- by using the shortcut key **Ctrl+R**

The dialog consists of three tab folders, which are described, in the next chapters:

Label Type

Paper and Label Size

[Number of QSO and Footer Lines](#)

Label Type

 You have the choice to select a **Custom Type Format** if you print on QSL cards or if you design own formats or if you can't find your label type in the **Standard Type Formats**. BV offers label formats of 31 different label suppliers and 1490 predefined label formats. Choose the product you use and click on "Next" to enter the [Paper and Label Size](#).

See also:

[Layout Settings](#)

[Paper and Label Size](#)

Paper and Label Size

 If you have selected a **Custom Type Format**, choose a **Paper Size** out of the drop-down-list of paper sizes. If you can't find your paper size (label sheet size) here, set it to *Custom Size* and enter the width and length of the label sheet afterwards.

All units here are based on the unit type (mm, inch or pixel) as set in the [Basic Designer Window Options](#).

Next, set the **Paper Margins** and the **Label Dimensions**, how many label **Columns** and **Rows** every label sheet has, and the **Space** between the single columns and rows if there is any.

If you print on QSL cards, the number of **Columns** and **Rows** is of course 1 with no **Space** between the columns and rows. As size of the paper you should register the size of your QSL card but keep in mind that some printers support only a certain minimum size, e.g. 140mm x 140mm. If the minimum size of the printer is greater than the dimensions of the QSL card, the printer minimum size has to be entered here instead.

The next step is to set [Number of QSO and Footer Lines](#).

See also:

[Layout Settings](#)

[Label Type](#)

[Number of QSO and Footer Lines](#)

Number of QSO and Footer Lines

 Set the **Number of QSO Lines** you want to print on each label here as well as the **Number of Footer Lines** (optional). If you need any space between the single QSO and footer lines, enter it into next fields **Space between QSO lines** and **Space between footer lines**.

A **Layout description and notes** is optional.

There are some automatic actions you can perform after you have finished registering all these parameters:

[Create layout template](#)

[Add missing fields automatically](#)

[Adjust all QSO and footer lines](#)

See also:

[Layout Settings](#)

[Label Type](#)

[Paper and Label Size](#)

Design Tips

Add missing fields automatically

 This function is helpful when you design complex labels with many QSO lines and especially when you design one from the scratch. Simply put the data fields of the first QSO row on the label, set the [Number of QSO and Footer Lines](#) tab of the [Layout Settings](#) and let this function create the missing data fields automatically for of the remaining QSO lines (and optionally footer lines).

The shortcut key is [Ctrl](#) + [A](#).

See also:

[Adjust all QSO and footer lines](#)

[Analyze layout settings](#)

[Create layout template](#)

[Layout Settings](#)

Adjust all QSO and footer lines

 This is a very helpful function. It adjusts all QSO and footer line fields automatically if you print more than one QSO line on the labels. The second, third and all further QSO lines fields are adjusted in reference to the position of the data field elements in the first QSO line. The data field in QSO line #1 with the highest top position determines the top position of all further QSO data fields in the layout. All QSO data fields of the same kind in the layout get the same "X" positions as the data fields in QSO line #1. The space between the single lines is defined in the [Number of QSO and Footer Lines](#) tab of the [Layout Settings](#).

The shortcut key is [Ctrl](#) + [J](#).

See also:

[Add missing fields automatically](#)

[Analyze layout settings](#)

[Create layout template](#)

[Layout Settings](#)

Analyze layout settings

 It can happen that the positions of some of the fields exceed the dimensions of the label area, which means that they are not within the printable area and not visible then in the printout. In this case you need to move these layout elements into the printable area. It is sufficient to move the data fields of the first QSO line, all following rows can automatically be adjusted to the new positions through the function [Adjust all QSO and footer lines](#).

This function is called automatically when a layout is loaded or saved. The shortcut key is [Ctrl+E](#).

See also:

[Add missing fields automatically](#)

[Adjust all QSO and footer lines](#)

[Create layout template](#)

[Layout Settings](#)

Create layout template

 This function creates automatically standard layout fields as set in the [Layout Settings](#). It can however happen that the positions of some of the fields exceed the size of the label, which means that they won't be in the printable area and not visible then in the printout. In this case you need to move these layout elements into the printable area. It is sufficient to move the data fields of the first QSO line, all following rows can automatically be adjusted to the new positions through the function [Adjust all QSO and footer lines](#).

The shortcut key for this function is [Ctrl+K](#).

Note: This function overwrites all existing elements in the layout, which means that the layout is first emptied before this function is performed!

See also:

[Add missing fields automatically](#)

[Adjust all QSO and footer lines](#)

[Analyze layout settings](#)

[Layout Settings](#)

BV Tools

BV Tools Overview

The **Tools Window** is the log import/export utility of **BV**. It imports 36 different logbook formats like ADIF (Amateur Data Interchange Format), any dBase, ASCII and CSV ("comma separated value" files), CT, NA, TRLog, WF1B and many others. It can export logs into 6 different formats.

Several input logs can be imported at one time.

Open the **Tools Window** via

- the main menu **Windows | Tools (Import/Export)** *or*
- by clicking on the  button in the main toolbar *or*
- by using the shortcut key `Ctrl+T`.

The **BV Tools Wizard** guides you through all necessary of the log import/export procedure.

See also:

[Import Log Types](#)

[Export Log Types](#)

BV Tools Wizard

BV Tools Wizard

The **Tools Window** is the log import and export section of **BV**. The procedure is basically the same for both import and export, one or several input files will be read, sorted (, merged) and written into one output file.

You are absolutely free in your choice of types and numbers of input logs. You can for example create one output log from maybe two CT logs, five BV logs and one ADIF log. No limits.

The **BV Tools Wizard** guides you through all necessary of the log import/export procedure. The first page contains two items to select,

- [Import/Export Logs](#) and
- Log Macros

Note: The Log Macros section is not yet available!

BV Tools Wizard - Choose Input Log(s)

You can import one or more logs from different sources. It is called *Input* here. The first step is to select the right **Log Type** for the data you want to import. The list of available log types that can be imported – together with notes to the single types - is listed in the chapter [Import Log Types](#).

After you have chosen the right log type, click on the [Add Log](#) button to select the log file(s) to be imported. You can select more than one file at one time in the open file dialog by holding the [Ctrl](#) key pressed and clicking on the files.

You can alternatively can *drag and drop* the files to be imported. Open the little [Explorer Window](#) by clicking on the [Explorer Window](#) button. First choose the drive in drive combo box. Select the folder in the directory box where your import files are located. Change a folder by double-clicking on a folder icon. All files, which match the log type's file extension, will be listed in the file list box. Click on a filename, keep the left mouse button pressed and move (drag) it into the file list box. You can choose several files at one time by keeping the [Ctrl](#) key pressed and selecting file names.

Every added log file will be added to the file list box and file name, call sign, log size etc. will be displayed in the grayed fields. Accidentally added log files can be removed from the import list by clicking on the [Remove item](#) button. Clicking on the [Clear list](#) button empties the entire list.

[Comment](#)

You can optionally add a different comment for every log you import by entering it into the comment field. This here registered comment appears later in the log and it can be printed on QSL labels as well. This is especially useful if you import several contest logs into one BV QSL database. A comment can for example be the contest name or contest abbreviation.

[Analyze log](#)

This option reads your log *before* it is imported and checks it for any errors.

[Next step](#)

After you have chosen at least one input log to be imported, click on the [Next](#) button to proceed. For ASCII and CSV, click on the [Specification](#) button to define the [ASCII and CSV File Import Specifications](#). For dBase log files, define the [DBase Import Specifications](#) before you proceed.

See also:

[Import Log Types](#)

[BV Tools Wizard - Choose Output Log](#)

BV Tools Wizard - Choose Output Log

[Log Type](#)

The list of available output log types– together with notes to the single types - is listed in the chapter [Export Log Types](#). The default is, of course, *BV (Logs Version 7)*.

[Save as](#)

Choose a file name for the output log file. The folder for BV logs may not be changed.

[Callsign](#)

Enter the call sign for the log. As long as you haven't entered a call sign, BV won't let you start the log conversion.

[Import QSO's between ... and ... \(optional\)](#)

Convert QSO's between and *and* edit fields let you optionally select on log records that fit into this date range at conversion time. The format is *yyyy.mm.dd*. If you type e.g. *2001.01.01* in the *Date From* field, only QSO's after Jan 1st, 2001 will be processed and written into the output log. Even typing just *2001* would be enough for this case. If you type *1999* in the *Date From* field and *20001231* in the *Date To* field,

all QSO's between Jan 1st, 1999 and Dec 31st, 2000 will be processed. If you leave the *Date From* field empty and fill out *Date To*, all log records until this specified end date will be processed (inclusive).

Import only QSO's which have a "QSL sent flag" = "No" (optional)

This option processes only those QSO's that have a *QSL sent flag* = *No*, which means that all other QSO's that were already confirmed are ignored and not imported.

Remove contest exchanges from report (optional)

This option "cleans" reports from any contest numbers or other exchanges - except when it is recognized as 59+ or 599+ reports, Meteor Scatter or EME QSO's. Useful for some import logs that provide reports together with the contest exchange and which looks nasty on the QSL label.

Replace contest reports with standard reports (59/599) (optional)

This option is necessary for some contest logs with non-standard exchanges like the Sweepstakes in TRLog.

- For ASCII output and G4ZFE Log Search Applets output, the fields to be exported have to be specified first. Click on the [Next](#) button to proceed.
- For all other log types, click on the [Start Conversion](#) button now to start the conversion.
- If the BV output log exists already, you have to specify whether you want to overwrite the existing log or update it in the [Write Mode](#) tab.

See also:

[BV Tools Wizard - Choose Input Log\(s\)](#)

[Export Log Types](#)

BV Tools Wizard - Specify fields to be exported

For ASCII output and G4ZFE Log Search Applets output, the fields to be exported have to be specified first.

Specify, which fields you want to export by checking the fields in the list box on the left. Dragging particular fields and dropping them at another position can change the field order.

Note: The field *X-Band QSO's* is for future use and not yet filled.

ASCII output

Specify in which format you prefer the ASCII type output. There are two general types, the *Delimited* type (characters separate each field) and the *Fixed Width* type (all fields are aligned in fixed columns).

Note: The *Fixed Width* type is not yet properly working!

Further format options are the *Field Delimiter* (tab, semicolon, comma) which is necessary for the *Delimited* type. The *Text Qualifier* (" or `) has to be specified if the field values shall be embedded in one of these characters. *Band information* can be exported in either bands (m) or frequency (MHz). The exact *Date Format* can be specified too. The default is *yyyymmdd*. Check the field *Field names header* if you want the field (column) names to appear in the first row of the ASCII output file.

Note: The *Field names header* function is not yet properly working!

G4ZFE Log Search Applets

For G4ZFE output, only the list of fields to be exported has to be checked and the *Date Format* can be specified *if* you export the date field, which is normally not done. The default for the *Date Format* is *yyyymmdd*.

Click on the [Start Conversion](#) button afterwards to start the [conversion](#).

See also:

[BV Tools Wizard - Choose Input Log\(s\)](#)

[BV Tools Wizard - Choose Output Log](#)

[Export Log Types](#)

BV Tools Wizard - Write Mode

If your output BV log should exist already, the BV Tools Wizard opens the **Write Mode** tab folder before you can begin to convert and asks you what to do:

'The output log file exists already! What do you want to do?'

You have three choices:

Append/Update log: update destination records

If a record exists already in the output log file (destination), it is updated from the input log file (source). The source has priority. If a record does not yet exist in the destination, it is added to the log.

Append/Update log: DO NOT update destination records

If a record exists already in the destination, it is NOT updated from the source. The destination has priority. If a record does not yet exist in the destination, it is added to the log.

Note: Both Append/Update modes check source and destination whether call sign, date, time, band, mode match. If a match is found, the destination is either updated *or* not updated. Both modes take *much* longer than the Overwrite mode.

Overwrite log

The Overwrite mode overwrites - as the word says - your whole log! So this can be dangerous.

After clicking on the [Start Conversion](#) button, you can finally perform the [log conversion](#) log conversion.

See also:

[BV Tools Wizard - Choose Input Log\(s\)](#)

[BV Tools Wizard - Choose Output Log](#)

[Export Log Types](#)

BV Tools Wizard - Converting...

After you have gone through all necessary steps of defining the input and the output, the output log is finally generated. A protocol tells how many QSO's were read and how many were written. Please note that the number of written QSO's can be smaller than the number of read QSO's because duplicate or QSO's having errors are excluded. If there were errors in the error logs, they are listed in an error log file, which can be viewed after the conversion. BV checks the imported logs for call sign, date, time, band and mode errors.

See also:

[BV Tools Wizard - Choose Input Log\(s\)](#)

[BV Tools Wizard - Choose Output Log](#)

BV Tools Wizard - Log Macros

This program function and help file chapter is not yet available!

ASCII, CSV and dBase Import Specifications

ASCII and CSV File Import Specifications

BV is able to import practically any type of ASCII and CSV log files but so-called **Import Specifications** need to be defined first.

ASCII Text Files [*[.txt](#)]

Very common log formats are text files (ASCII files). There are usually two types – one is the *fixed format type* where all fields are aligned in fixed columns and the other one is the *delimited type* where all fields are separated by delimiters, e.g. colons.

CSV (Comma separated values) [*[.csv](#)]

Microsoft Excel can generate CSV files but these files are nothing else than ASCII files of the *delimited type* where all fields are separated by delimiters, e.g. colons, and all values are embedded in hyphens.

See also:

[ASCII and CSV File Import Specifications - Specifications](#)

[ASCII and CSV File Import Specifications - Text Type](#)

[ASCII and CSV File Import Specifications - Delimited File Type](#)

[ASCII and CSV File Import Specifications - Fixed File Type](#)

[ASCII and CSV File Import Specifications - Field Mapping](#)

ASCII and CSV File Import Specifications - Specifications

If you import an ASCII or CSV file for the first time, enter a *new* import **specification name** and click on **Next step**. If it is a *repeated* import, choose an already existing specification from the list box below and click on **OK**.

See also:

[ASCII and CSV File Import Specifications - Text Type](#)

[ASCII and CSV File Import Specifications - Delimited File Type](#)

[ASCII and CSV File Import Specifications - Fixed File Type](#)

[ASCII and CSV File Import Specifications - Field Mapping](#)

ASCII and CSV File Import Specifications - Text Type

A sample of the first few lines of the file is displayed.

Text type

Try to determine the *Text type* of the file to be imported by looking at this sample or by clicking on the **Analyze** button. The analyzer tries to determine the type automatically by trying to find certain patterns.

There are usually two types – one is the *delimited type* where all fields are separated by delimiters, e.g. colons and the other one is the *fixed format type* where all fields are aligned in fixed columns.

Field Delimiter

Mainly for the *delimited type*, have a look and specify what kind of *field delimiter* is used to separate the fields from each other. Delimiters are usually tab, semicolon (;), colon (,), space or any other character you enter.

Text Qualifier

If the single field values are embedded in certain characters, usually hyphen or double-hyphen, specify them in the *text qualifier* combo box. Otherwise choose *none*.

File has header row

Check this if the file has one or more header rows. The names of the fields (columns) are often listed in header rows.

See also:

[ASCII and CSV File Import Specifications - Specifications](#)

[ASCII and CSV File Import Specifications - Delimited File Type](#)

[ASCII and CSV File Import Specifications - Fixed File Type](#)

[ASCII and CSV File Import Specifications - Field Mapping](#)

ASCII and CSV File Import Specifications - Delimited File Type

If you are importing the *delimited type*, this tab folder displays the first 20 lines of the file in a data grid. This is just for testing purposes. If anything looks strange or if there is only one single column displayed, then there is something wrong with your definitions and you should go back to the **Text Type** tab folder to

correct it. If everything looks OK, proceed to the final step, the [Field Mapping](#) tab folder by clicking on the [Next step](#) button.

See also:

[ASCII and CSV File Import Specifications - Specifications](#)

[ASCII and CSV File Import Specifications - Text Type](#)

[ASCII and CSV File Import Specifications - Fixed File Type](#)

[ASCII and CSV File Import Specifications - Field Mapping](#)

ASCII and CSV File Import Specifications - Fixed File Type

In the *fixed format type* all fields are aligned in fixed columns. When this tab folder is opened, the wizard has made some guesses about where the field breaks occur. They are highlighted in red. Check that they are correct. If not, you can make adjustments:

- to *create* a break line, click at the desired position
- to *delete* a break line, double click on the line
- to move a break line, click and drag it

If everything looks OK, proceed to the final step, the [Field Mapping](#) tab folder by clicking on the [Next step](#) button.

See also:

[ASCII and CSV File Import Specifications - Specifications](#)

[ASCII and CSV File Import Specifications - Text Type](#)

[ASCII and CSV File Import Specifications - Delimited File Type](#)

[ASCII and CSV File Import Specifications - Field Mapping](#)

ASCII and CSV File Import Specifications - Field Mapping

Go through all available source fields in the left column and try to assign them to the corresponding fields of the combo boxes in the right column.

Do not forget to set the [Date Format](#) and determine the format of the [Band/Freq Information](#).

Finally, click on the [OK](#) button to save the specification and to close the dialog.

Note: The [OK](#) button is enabled as soon as you have assigned at least the fields call, date, time, band and mode!

See also:

[ASCII and CSV File Import Specifications - Specifications](#)

[ASCII and CSV File Import Specifications - Text Type](#)

[ASCII and CSV File Import Specifications - Delimited File Type](#)

[ASCII and CSV File Import Specifications - Fixed File Type](#)

[Date Format](#)

[Band/Freq Information](#)

DBase Import Specifications

BV is able to import practically any type of dBase log files but so-called **Import Specifications** need to be defined first.

dBase [*.dbf]

DBase is also very popular. Dbf files are tables consisting of columns (fields) and (data) rows. The fields and field contents to be imported are to be specified before you import.

See also:

[DBase Import Specifications - Specifications](#)

[DBase Import Specifications - Field Mapping](#)

DBase Import Specifications - Specifications

If you import a dBase file for the first time, enter a *new* import **specification name** and click on **Next step**. If it is a *repeated* import, choose an already existing specification from the list box below and click on **OK**.

See also:

[DBase Import Specifications - Field Mapping](#)

DBase Import Specifications - Field Mapping

Go through all available source fields in the left column and try to assign them to the corresponding fields of the combo boxes in the right column.

Do not to forget to set the **Date Format** and determine the format of the **Band/Freq Information**.

Finally, click on the **OK** button to save the specification and to close the dialog.

Note: The **OK** button is enabled as soon as you have assigned at least the fields call, date, time, band and mode!

See also:

[DBase Import Specifications - Specifications](#)

[Date Format](#)

[Band/Freq Information](#)

Date Format

The date display format of the date field of your import log has to be defined when you compile the specifications for **dBase** and **ASCII/CSV** files. The date format consists of abbreviations for year (y), month (m) and day (d) and separators (e.g. ".", "-").

Enter the correct date format string in the **Date format** edit field. Take a look the date field of your data,

- determine first the order of day, month and year
- determine how many digits the year has (two or four) and
- finally determine the separator between day, month and year, if existent.

Common formats are e.g. *yyyymmdd* or *dd.mm.yy*.

See also:

[Band/Freq Information](#)

Band/Freq Information

The band information type of the band/frequency field of your import log has to be defined when you compile the specifications for **dBase** and **ASCII/CSV** files. This is necessary because otherwise 10m and 10MHz could be mixed up.

Choose

- either band information (m) if you are sure that your log contains band information only,
- or frequency information (MHz) if you are sure that your log contains frequency information only,
- or band or frequency (m/MHz) if you don't know or have both (which is not good).

See also:

[Date Format](#)

Log Types

Import Log Types

BV is able to import these log types. Some log types, which were available in BV Version 6, are no more offered in BV Version 7 or can be differently imported.

ADIF (Amateur Data Interchange Format) [*.adi]

ADIF is meanwhile the most common log interchange format. See the description in the chapter **ADIF - Amateur Data Interchange Format** and notes to the import in BV in the chapter **ADIF Import into BV**.

ARMAP99 [*.csv]

ARMAP99 cannot be imported directly but use the CSV import instead. See the chapter **ASCII and CSV File Import Specifications**.

ASCII Text Files [*.txt]

The second most commonly used format is text files (ASCII files). There are usually two types – one is the *fixed format type* where all fields are aligned in fixed columns and the other one is the *delimited type* where all fields are separated by delimiters, e.g. colons. BV is able to import practically any type of ASCII text files of both types but so-called **ASCII File Import Specifications** need to be defined. See the chapter **ASCII and CSV File Import Specifications**.

BV Files Version 3 to 6

For backward compatibility and upgrade reasons, log files from former version of BV can be imported of course. BV Version 3 files (DOS) had the file extensions *.qsl and *.srt, BV Version 4 files (DOS) *.bv1 and *.bv2, BV Version 6 files (Windows) the extensions *.dbf, *.mdx and *.bvc.

BV Logs (Version 7)

BV logs of Version 7 (*.dbf, *.mdx, *.bv7) can be imported of course.

Cabrillo [* .txt]

Cabrillo format, developed by N5KO, becomes the second most important interchange format. Cabrillo is the required log format for the most important contests. Most contest programs generate Cabrillo output. CT by K1EA for example generates the file *callsign.txt* when you enter the command *WRITELOG* in the call sign field.

CSV (Comma separated values) [* .csv]

Microsoft Excel can generate CSV files but these files are nothing else than ASCII files of the *delimited type* where all fields are separated by delimiters, e.g. colons, and all values are embedded in hyphens. BV is able to import practically any type of CSV files but so-called **CSV File Import Specifications** need to be defined. See the chapter **ASCII and CSV File Import Specifications**.

CT by K1EA

There are two ways to import log files from CT. Use the CT text command *WRITELOG* that creates the **Cabrillo** file *callsign.txt*. This one can be imported into BV. Alternatively you can use the CT utility program C2A, provided by Jim Reisert, AD1C, which converts the CT log file [* .bin] into **ADIF** [* .adi]. Call C2A together with the log file name in a DOS session. Be sure to use the latest version of C2A from the CT website www.k1ea.com.

dBase [* .dbf]

BV is able to import practically any type of dBase files but so-called **dBase Import Specifications** need to be defined.

DX4WIN

DX4WIN cannot be imported into BV. Use the ADIF export of DX4WIN instead.

DXBase [* .sdf]

DXBase cannot yet be imported into BV Version 7.

DXLog by DL2SCJ (ASCII Format) [* .log]

DXLog cannot yet be imported into BV Version 7.

FINTTEST [* .txt]

FINTTEST cannot yet be imported into BV Version 7.

G4ZFE Log Search Applet

The G4ZFE log search files cannot be imported but exported.

HAM-LOG

HAM-LOG cannot yet be imported into BV Version 7.

Ham System by OH2GI

Ham System cannot yet be imported into BV Version 7.

Kenwood HamWindows

HamWindows import has been removed but I can provide a separate conversion utility on request.

LOGPlus! by N7XR (KD7P)

The LogPlus! files are dBase and can be imported with the dBase import. **Import Specifications** are provided with the BV distribution.

LOGic

LOGic cannot yet be imported into BV Version 7.

NA by K8CC (PRN Files)

NA can directly be imported into BV Version 7.

OH1AA (.ASC Files)

OH1AA files cannot yet be imported into BV Version 7.

QW by DL4MFM (.BIN Files)

QW can directly be imported into BV Version 7.

R25Log

The R25Log files are dBase and can be imported with the dBase import. **Import Specifications** are provided with the BV distribution.

RTTY by WF1B Contest Software [*bin]

RTTY logs can directly be imported into BV.

SPLog

SPLog import has also been removed.

SPRINT by DL2NBU [*asc]

SPRINT logs can directly be imported into BV.

Swisslog

The DOS version of Swisslog can directly be imported into BV but the Windows version not. Use the ADIF export of the Windows version instead.

TRLog by N6TR

TRLog log files can directly be imported.

Toplog by I4UFH (Version 3)

The Toplog logs are dBase and can be imported with the dBase import. **Import Specifications** are provided with the BV distribution.

WB2DND (N1DG) Log Database

The WB2DND logs are dBase and can be imported with the dBase import. **Import Specifications** are provided with the BV distribution.

Writelog

Writelog cannot be imported into BV. Use the ADIF export of Writelog instead.

YPLog by VE6YP

YPLog log files can directly be imported.

Export Log Types

BV is able to export these log types. Please be aware that some of the data gets lost when exporting, for example contest exchanges, because BV has a "smaller" data model and stores only what is needed for QSL printing and management.

[ASCII Format - sorted by date \[*.txt\]](#)

A very frequent and easy type is the ASCII format exported as text files. At export time you can select in a special tab folder which fields you want to export. The output is sorted by date and time.

[ASCII Format - sorted by calls \[*.txt\]](#)

The same applies to this type except that the output is sorted by call signs.

[ADIF \(Amateur Data Interchange Format\) \[*.adi\]](#)

ADIF is meanwhile the most common log interchange format. See the description in the chapter [ADIF - Amateur Data Interchange Format](#).

[BV Logs \(Version 7\)](#)

This output type is the default of course. The logs consist of three files with the extensions *.dbf, *.mdx and *.bv7). They are located in the sub folder *logs* of the BV program folder.

[Cabrillo \[*.txt\]](#)

Cabrillo format, developed by N5KO, becomes the second most important interchange format. Cabrillo is the required log format for the most important contests. Please be aware that some of the data can get lost, mainly the contest exchanges.

[G4ZFE Log Search Applet](#)

This export creates a directory named by the call sign to be exported and by default in the sub folder *tmp*. It then writes all QSOs into 36 text files named 0.txt to 9.txt and a.txt to z.txt (well, not very nice but that's required). Which fields are to be exported and their sort order can be set in a special tab folder.

ADIF - Amateur Data Interchange Format

[ADIF – Amateur Data Interchange Format](#)

Ever since software has become a part of amateur radio, there have been as many data formats as there have been ham radio software programmers. Hams have struggled with converting data among various formats. Several hams have been discussing such a standard via an Internet discussion. In early 1996 KK7A promoted the idea of a standard for exchange of ham data. An Internet reflector was set up for discussing such a standard. WF1B and WN4AZY, as publishers of commercial ham radio software, have taken the best suggestions from this discussion and formed a proposal. Ray introduced it at the 1996 Dayton Hamvention. Within a year, this proposal has adapted adopted by most software publishers.

[ADIF – Format Description](#)

Each data field is preceded by a field name and length enclosed in angle brackets ("tags"). A colon separates the name and length. The field name may be in upper, lower, or mixed case. Case is insignificant. For instance, CALL, Call, or call is equivalent. The length specification is ASCII text in display format, and may be of any non-negative value. The data follows the closing angle bracket. For example:

```
<CALL:5>DF3CB
```

Records are made up of multiple fields and terminated with <EOR> or <eor> as an end-of-record marker. For example:

```
<call:5>DF3CB<band:4>160M<mode:2>CW<qso_date:8>20000513<time_on:4>2359<eor>
```

An optional field type indicator may follow the field length, separated by a colon: For example:

```
<qso_date:8:d>19960513
```

The field type indicator may be in upper, lower, or mixed case. A field type indicator is optional. For instance, the field definition for QSO_DATE specifies that the field is always of type Date, so it is not necessary to repeat it here. However, when exporting user-defined fields that are not part of the ADIF specification, a type indicator will assist anyone attempting to import the data.

Any number of characters of any value except < may be added after a field's data or <eor> and before the start of the next field. This is typically carriage returns and/or line-feeds to make the file easier to read in a text viewer. For example:

```
<call:5>DF3CB <band:4>160M <mode:2>CW  
<qso_date:8>20000513 <time_on:4>2359 <eor>
```

For full ADIF information and specifications see the ADIF homepage at:
<http://www.hosenose.com/adif/index.htm>

See also:

[ADIF Import into BV](#)

ADIF Import into BV

ADIF and BV

BV supports the following ADIF tags for import and export:

<call:n>	max. 16 characters
<qso_date:8:d>	yyyymmdd, e.g. 20011231
<time_on:4>	hhmm, e.g. 2359
<band:n>	160M, 80M, 40M, and so on. See: Supported Bands for a complete list.
<mode:n >	CW, SSB and so on. See Supported Modes and Sub Modes for a complete list.
<submode:n >	See Supported Modes and Sub Modes .
<rst_sent:n >	up to 6 digits
<rst_rcvd:n >	up to 6 digits
<qsl_sent:n >	Y (= yes), N (= no), B (= bureau), D (= direct), I (= ignore/invalid), ! (= never send QSL),
<qsl_rcvd:n >	Y (= yes), N (= no), B (= bureau), D (= direct), I (= ignore/invalid), ! (= never will receive QSL),
<qslsdate:8:d>	Date QSL sent, yyyymmdd, e.g. 20011231
<qslrdate:8:d>	Date QSL received, yyyymmdd, e.g. 20011231
<comment:n >	max. 60 characters
<dxcc:n >	DXCC reference number
<freq:n >	max. 12 characters
<qsl_via:n >	QSL manager info
<sat_name:n >	e.g. AO-10
<sat_mode:n >	e.g. 2m/70cm

[Import of other ADIF fields](#)

Besides this, you can choose another ADIF identifier from your ADIF import file, which shall be assigned to the field "COMMENT" in BV at import time. This can be any of the ADIF tags

<COMMENT>	Comment field for QSO
<ADDRESS>	As it will appear on the mailing label
<ARRL_SECT>	ARRL section
<CNTY>	US County (STATE,COUNTY)
<CONT>	Continent: NA, SA, EU, AF, OC, AS
<CONTEST_ID>	Contest identifier -- CQWW, ARRLDX, etc.
<CQZ>	CQ Zone
<DXCC>	Numeric identifiers from ARRL
<GRIDSQUARE	Grid Locator
>	
<IOTA>	Example: NA-001
<ITUZ>	ITU Zone
<NAME>	Name
<NOTES>	Long text
<OPERATOR>	Call sign of person logging the QSO
<PFX>	WPX prefix
<QLMSG>	Personal short message to appear on QSL card
<QSLRDATE>	QSL Rcvd Date
<QSLSDATE>	QSL Sent Date
<QSL_VIA>	via QSL Manager
<QTH>	QTH
<SAT_MODE>	Satellite Mode
<SAT_NAME>	Name of satellite
<SRX>	Received serial number for a contest QSO
<STATE>	US state
<STX>	Transmitted serial number for a contest QSO
<TEN_TEN>	TenTen Number
<VE_PROV>	2-letter abbreviations: AB, BC...

Default field is <COMMENT>. You can set it if you click on the **ADIF Options** button right to the Input Log Type combo box. Click on the **OK** button afterwards.

Other Notes

Longer texts than 60 characters will be truncated because the BV field "COMMENT" is 60 characters wide.

QSO's marked with <QSL_SENT:1>R (R = requested) will be automatically marked (highlighted in red) and can be printed separately when you filter for marked QSO's.

Satellite QSO's

The ADIF tag <BAND:3>SAT is required for Satellite QSO's. The Satellite's name can be supplied with the ADIF tag <SAT_NAME:n> (max length 6) - for example: <SAT_NAME:5>AO-10 - and the Satellite's mode with the ADIF tag <SAT_MODE:n> (max length 9) - for example: <SAT_MODE:7>2m/70cm. Both tags are combined and put into BV log column "COMMENT". The comment (Satellite info) can be printed on labels then.

See also:

[ADIF - Amateur Data Interchange Format](#)

Supported Bands

BV complies with the band and mode designation rules as defined in the ADIF (Amateur Data Interchange Format) specifications. See <http://www.hosenose.com/adif/index.htm> for all details.

The bands that can be used with BV are:

- 160m (1.8 MHz)
- 80m (3.5 MHz)
- 40m (7 MHz)
- 30m (10.1 MHz)
- 20m (14 MHz)
- 17m (18 MHz)
- 15m (21 MHz)
- 12m (24.9 MHz)
- 10m (28 MHz)
- 6m (50 MHz)
- 4m (70 MHz)
- 2m (144 MHz)
- 1.25m (220 MHz)
- 70cm (432 MHz)
- 35cm (902 MHz)
- 23cm (1300 MHz)
- 13cm (2300 MHz)
- 9cm (3300 MHz)
- 6cm (5660 MHz)
- 3cm (10 GHz)
- 1.25cm (24 GHz)
- 6mm (47 GHz)
- 4mm (75 GHz)
- 2.5mm (120 GHz)
- 2mm (142 GHz)
- 1mm (241 GHz)
- SAT (Satellite)

Modes and Sub Modes in BV

Supported Modes and Sub Modes

BV complies with the band and mode designation rules as defined in the ADIF (Amateur Data Interchange Format) specifications. See <http://www.hosenose.com/adif/index.htm> for all details. The following modes can be used with BV. The designations in particular are:

- SSB
- CW
- RTTY
- TOR (AMTOR)
- PKT (Packet)
- AM
- FM
- SSTV
- ATV
- PAC (Pactor)
- CLO (Clover)
- PAC2 (Pactor II)
- GTOR (Golay TOR (GTOR))
- FSK31
- PSK31
- PSK63
- PSK125
- MT63
- MFSK8
- MFSK16
- HFSK
- MTTY (Mini RTTY (MTTY))
- THRB (THROB)
- ASCI (ASCII)
- HELL (Hellschreiber)

- Q15 (Q15X25)
- PCW (Precision CW)
- WSJT
- FAX

Note: the modes WSJT and FAX are missing in the original Proposed Changes of the ADIF specifications (http://www.hosenose.com/adif/proposed_changes.htm). They were added in BV.

There are meanwhile so many new digital modes, which are actually variations of a main mode, so that a new field (column) called **Sub Mode** was introduced. The sub modes are in particular:

Main Mode	Sub Mode	Description
CLO	FEC-2DPSM	CLOVER FEC-2DPSM
CLO	FEC-BPSM	CLOVER FEC-BPSM
CLO	FEC-QPSM	CLOVER FEC-QPSM
CLO	FEC-8PSM	CLOVER FEC-8PSM
CLO	FEC-8P2A	CLOVER FEC-8P2A
CLO	FEC-16P4A	CLOVER FEC-16P4A
CLO	ARQ-BPSM	CLOVER ARQ-BPSM
CLO	ARQ-QPSM	CLOVER ARQ-BPSM
CLO	ARQ-8PSM	CLOVER ARQ-8PSM
CLO	ARQ-8P2A	CLOVER ARQ-8P2A
CLO	ARQ-16P4A	CLOVER ARQ-16P4A
FAX	FAX480	FAX 480
FAX	AMFAX	AMFAX
FAX	FMFAX	FMFAX
HELL	FH	Feld-Hell
HELL	PSKH	PSK-Hell
HELL	DH	DUPLO-Hell
HELL	FMH	FM-Hell
HELL	FSKH	FSK-Hell
HELL	SFH	SLOW-FELD Hell
HELL	CMT	Concurrent Multi Tone Hell

HELL	SMT	Sequential Multi Tone Hell
PAC	UNP	PACTOR 1 UNPROTO
PAC	PARQ	PACTOR ARQ
PAC2	UNP2	PACTOR2 UNPROTO (DPSK)
PAC2	DBPSK	PACTOR 2 ARQ -- DPSK
PAC2	DQPSK	PACTOR 2 ARQ -- DQPSK
PAC2	8DPSK	PACTOR 2 ARQ – 8DPSK
PAC2	16DPSK	PACTOR 2 ARQ -- 16DPSK
PSK31	BPSK	PSK31 BPSK
PSK31	QPSK	PSK31 QPSK
SSTV	Martin1	SSTV Martin1
SSTV	Martin2	SSTV Martin2
SSTV	Scottie1	SSTV Scottie1
SSTV	Scottie2	SSTV Scottie2
SSTV	ScottieDX	SSTV ScottieDX
SSTV	AVTBW	SSTV AVT B&W
SSTV	AVT24	SSTV AVT24
SSTV	AVT90	SSTV AVT90
SSTV	AVT94	SSTV AVT94
SSTV	AVT188	SSTV AVT188
SSTV	HQ1	SSTV HQ1
SSTV	HQ2	SSTV HQ2
SSTV	P3	SSTV P3
SSTV	P5	SSTV P5
SSTV	P7	SSTV P7
SSTV	PD50	SSTV PD50
SSTV	PD90	SSTV PD90
SSTV	PD120	SSTV PD120
SSTV	PD160	SSTV PD160
SSTV	PD180	SSTV PD180

SSTV	PD240	SSTV PD240
SSTV	PD290	SSTV PD290
SSTV	Robot BW8	SSTV Robot B&W 8
SSTV	Robot BW12	SSTV Robot B&W 12
SSTV	Robot BW24	SSTV Robot B&W 24
SSTV	Robot BW36	SSTV Robot BW36
SSTV	Robot C12	SSTV Robot Colour 12
SSTV	Robot C24	SSTV Robot Colour 24
SSTV	Robot C36	SSTV Robot Colour36
SSTV	Robot C72	SSTV Robot Colour72
SSTV	WraSC2-30	SSTV WraaseSC-2 30
SSTV	WraSC2-60	SSTV WraaseSC-2 60
SSTV	WraSC2-120	SSTV WraaseSC-2 120
SSTV	WraSC2-180	SSTV WraaseSC-2 180
TOR	FEC	AMTOR FEC
TOR	SELFEC	AMTOR SELFEC
TOR	AARQ	AMTOR ARQ

Note: When you import the mode **BPSK** or **QPSK** into BV, it is automatically assigned to the mode PSK31 and sub mode BPSK or QPSK. This is an exception. You should take care that the sub mode column is then visible in the log grid and that you add the field **sub mode** to your label layout. All other sub modes are *not* automatically assigned to the right mode and sub mode fields! Check that your ADIF export program takes care of this.

Note: The sub mode fields are *not* validated at import time and the BV log statistics do not list the sub modes separately.

Bands in BV

BV QSL Manager Database

QSL Manager Database

An important feature is the management of **QSL Manager Information** and printing QSL Manager info onto the label if a station has a manager. At the first program start of BV, a new, **empty** manager database is installed in the new subfolder 'manager' of the BV6 program folder.

The QSL Manager database is valid for all logs and therefore not stored for each single QSO. *I do not provide any QSL manager databases and will never do so!*

The maintenance of the QSL Managers database is done in a separate window – the [QSL Manager Window](#). At installation time the database is empty. Open the manager window by either

- double-clicking in the manager edit field in the search toolbar or
- via the main menu [Windows | QSL Manager](#) or
- with the short cut key [Ctrl+M](#)

Unchecking the checkbox ‘Use BV QSL Manager Database’ on the tab folder ‘directories’ of the Configuration Window can disable the QSL Manager support.

[QSL Manager Window](#)

[QSL Manager Import](#)

[Printing the QSL Manager on Labels](#)

QSL Manager Window

The **QSL Manager Window** has a data grid and displays the entire manager database. You are always free to enter, change and delete QSL Manager information as needed.

[QSL Managers](#)

[QSL Manager Import](#)

[Printing the QSL Manager on Labels](#)

QSL Manager Import

You have five possibilities of **filling and maintaining the database**:

1.) Enter QSL Manager information manually

in the field 'Manager' in the search toolbars of the main log window. If you enter a manager call there, it will be added to the database automatically. By scrolling through the log you can immediately see whether the station in the log has a manager. Otherwise the manager field remains empty. Delete a manager by emptying the manager field and pressing [Enter](#). If a DX station had several managers over the time, the manager's call is highlighted in red!

2.) Import QSL Manager information

together with your imported logs. Supported import types so far are ADIF (via the ADIF tag `<QSL_VIA> = QSL Manager`) and Logplus! Others will follow as long as the QSL Manager information is stored in the log. Check your logbook program to see if it is able to export QSL Manager information.

3.) Import other databases.

The import of the huge and very well maintained QSL Manager database of Martin, OK1RR, is provided and recommended. It has more than 150,000 entries! This was certainly a tremendous work over many years and we appreciate that very much. You find Martins database as a zipped file at <http://www.qsl.net/ok1rr>.

Unpack the ZIP file somewhere on your hard disk and locate it after clicking on the 'Import Manager' button in the tab folder 'QSL Managers' of the Tools Window. The conversion might take a few minutes time.

Repeated manager imports are possible, they don't overwrite the database but update it.

4.) Import of QSL Manager information as ASCII files.

The format of the ASCII import files is very simple:

DX Call;Manager;Active;

For example:

1A0KM;I0IJ;1980;
1A0KM;IK0FVC;1993;

'Active' means the year (or even the exact date with 8 digits in the form `yyyymmdd`) the manager started his QSL manager function for the DX station. This is not required except for cases where a DX station had different, changing managers over the years. The first manager's entry doesn't need a start year but all consecutive managers so that BV can determine the right managers call based on the log date. Therefore it may look like this:

1A0KM;I0IJ;;
1A0KM;IK0FVC;1993;

Another supported Manager import file type is the **DX4WIN file format** (comma separated file):

CALL,<possibly date>,MANAGER

For example:

J49WI,,I2WIJ
AL7MQ,,DF3CB
4U1UN,,WB8LFO
4U1UN,04/01/1997,W6TER

5.) Import QSL Manager information together with your imported logs

Supported import types are ADIF (tag `<QSL_VIA>` via QSL Manager) so far and others will follow.

CAUTION: Please note that you can possibly print wrong QSL Manager information on your labels if a DX station had **different, changing managers** over the years! Back to the example above: if you print a QSO for 1A0KM in the year 1985, the program will choose I0IJ. If you print a QSO for 1A0KM after 1993 (inclusive), it will choose IK0FVC. If you will print all your 1A0KM QSO's at once, it will choose IK0FVC, the last found manager but IK0FVC will not confirm your QSO's prior to 1993. So, take care at

this point! The program and its author are in no way responsible for wrong information printed as only an empty database is provided!

[QSL Managers](#)

[QSL Manager Window](#)

[Printing the QSL Manager on Labels](#)

Printing the QSL Manager on Labels

At label print time the manager is printed onto the label if the station has one. The phrase 'via: ' is added automatically then. This is the default. The default can be changed to any other phrase or no phrase in the field 'Manager Text' of the tab folder 'Print Formats' in the [Configuration - Print Formats](#).

To print the QSL Manager information, add the field 'MANAGER' to your QSL Label Design first.

- Click on the **Add Data Field** button in the designer,
- place it on an appropriate place on the label and
- assign the field name **MANAGER** to it.
- Save your label design and test it.

[QSL Managers](#)

[QSL Manager Window](#)

[QSL Manager Import](#)

Appendix Glossary

Index

A

Add fields automatically	56
ADIF	66, 67, 68, 69, 70
ADIF Import into BV	70
Adjust all QSO lines.....	56
Amateur Data Interchange Format	66, 69
Analyze button	63
Analyze layout settings	57
Answering	23
SWL QSL Cards	23
Append/Update	61
ARMAP99	67
Arranging	40
Log Windows	40
ASCII Code.....	27, 28
ASCII Format.....	66
ASCII Text Files	62, 67
Auto Open Logs	28

B

Background Color	37
Band Format	27
Band/Freq Information.....	66
Basic Designer Window Options	41
BDE	7, 28
BIN Files	66
Bitmaps	53
Borland Database Engine.....	7, 28
BV Label Designer.....	38
BV Logs	69
BV Step-by-Step	8
BV Tools Overview	57
BV Tools Wizard	58, 59, 60, 61, 62
BV Version 7	4
BV6to7	7

C

Cabrillo	67, 69
Callsign	59
Choose Input Log.....	58
Choose Output Log	59
Close log	16
Column Lines.....	37
Column Titles.....	37
Columns	37, 38, 55
Combo Boxes.....	25
Command Overview	12
Configuration	24, 25, 27, 28
Configuration Overview.....	24
Converting.....	61

Copyright Information	6
Create layout template.....	57
Creating.....	45
New Layouts	45
Csv	67
CSV.....	62
CSV File Import Specifications	62, 63, 64, 65
CT	67
Custom Size	55
Custom Type Format.....	46, 54, 55
D	
Data Alignment	37
Data Fields	48
Date Display Format	27
Date Format	27, 66
DBase	65, 67, 68, 69
DBase Import Specifications.....	65
Delimited File Type	63
Design Grid	41
DF3CB	4
DX4WIN	67
DXBase	67
DXLog	67
E	
Empty Print Queue	20
Export Log Types.....	69
Expressions	50
F	
F2	16
F2/F3	24
F3	16
Field Delimiter	63
Field Mapping	64, 65
Fill	16, 17, 18
Print Queue	16, 17, 18
Fill Print Queue	34
Filter	30
QSL sent.....	30, 31
Filter marked QSO s.....	31
FINTTEST	67
Fixed File Type	64
Footer Lines	36, 37, 55
Foreword	4
G	
G4ZFE Log Search Applet	68, 69
G4ZFE Log Search Applets	60
H	
Ham System	68
HAM-LOG	68
HamWindows	68
Handling.....	42

Elements	42, 43, 44
I	
Images	53
Import	9
first log	8
Import Log Types	66
Import Specifications	62, 65
Import/Export	38, 57, 58
Installation	7
Introduction	4
J	
JPEG	53
Jumping	40
between Log Windows	40
L	
Label Designer	38, 40
Label Designer Command Overview	46
Label Designer Introduction	40
Label Designer Window	38, 40
Label Dimensions	55
Label Frame Properties	48
Label Layout	46
Modifying	46
Label Print Options	18
Label Size	55
Label Type	54
Layout Elements	41, 44
Layout Settings	45, 54
Log	11
Navigating through	11
Log Grid Setup	37
Log Index	21
Log Macros	62
Log Navigation	32
Log Search	10
Log Statistics	36
Log Type	58, 59
Log Window	10, 40
Arranging	40
LOGic	68
LOGPlus	68
M	
Main Program Window	9
Manager Window	39
Mark QSO	35
Marking	35
Memo Fields	52
Modifying	46
Label Layout	46
N	
New Layout Definition Wizard	45

New Layouts	45
New log	15
Number	55
Footer Lines	55
QSO Lines	55

O

OK1RR	78
Open log	15
Overview	7
Overwrite	61

P

Page	41
Paper Margins	55
Paper Size	55
Predefined Settings	37
Print Formats	27
Print Labels	19
Print on QSL	46
Print Preview	19
Print Queue	11, 18
Fill	18
Print Queue Window	39
Printer Setup	20
Properties	42, 44
PSE/TNX	27

Q

QSL	30, 31
sent/received	30, 31
QSL Manager	34, 35, 80
Printing	79
QSL Manager Database	39, 77
QSL Manager Import	78
QSL Manager Window	78
QSO Edit Window	39
QSO Lines	55

R

Remove all QSO Marks	35
Reset all Dock Positions	40
Rows	55

S

Sample.adi	8
Sample.bvd	40
Satellite QSO s	70
Search	28, 29
Call	28, 29
Select all QSO s	33
Select row down	32
Select row up	33
Selected QSO s	34
Selecting	32
QSO records	32

Set QSL received flags	22
Set QSL sent flags	22
Set QSL sent/rcvd date	23
Shapes	52
Show Print Queue status	20
Slashed Zero	27
Sorting	25
Specifications	63, 65
Specify fields	60
SPRINT	68
Standard Type Format	46, 54
Submode	73
Supported Bands	72
Supported Modes	73
Swisslog	68
T	
Text Elements	49
Text Qualifier	63
Text Type	63
Time Format	27
Toggle Log Display Index	21
Toggle QSL sent/received flags	36
Tools Window	38, 57
Toplog	68
TRLog	68
U	
Unselect	33
Use BV QSL Manager Database	25
W	
WF1B Contest Software	68
Wipe search fields	31
Write Mode	61
WRITELOG	69
Y	
YPLog	69